

# Flex\_extract v7.1 – A software package to retrieve and prepare ECMWF data for use in FLEXPART

Anne Philipp<sup>1,2</sup>, Leopold Haimberger<sup>2</sup>, and Petra Seibert<sup>3</sup>

<sup>1</sup>Aerosol Physics & Environmental Physics, University of Vienna, Vienna, Austria

<sup>2</sup>Department of Meteorology and Geophysics, University of Vienna, Vienna, Austria

<sup>3</sup>Institute of Meteorology, University of Natural Resources and Life Sciences, Vienna, Austria

**Correspondence:** Anne Philipp (anne.philipp@univie.ac.at)

**Abstract.** Flex\_extract is an open-source software package to efficiently retrieve and prepare meteorological data from the European Centre for Medium-Range Weather Forecasts (ECMWF) as input for the widely-used Lagrangian particle dispersion model FLEXPART and the related trajectory model FLEXTRA. ECMWF provides a variety of data sets which differ in a number of parameters (available fields, spatial and temporal resolution, forecast start times, level types etc.). Therefore, the selection of the right data for a specific application and the settings needed to obtain them are not trivial. Consequently, the data sets which can be retrieved through flex\_extract by both authorised member-state users and public users as well as their properties are explained. Flex\_extract 7.1 is a substantially revised version with completely restructured code, mainly written in Python3, which is introduced with all its input and output files and an explanation of the four application modes. Software dependencies and the methods for calculating the native vertical velocity  $\dot{\eta}$ , the handling of flux data and the preparation of the final FLEXPART input files are documented. Considerations for applications give guidance with respect to the selection of data sets, caveats related to the land-sea mask and orography, etc. Formal software quality-assurance methods have been applied to flex\_extract. A set of unit and regression tests as well as code metric data are also supplied. A short description of the installation and usage of flex\_extract is provided in the appendix. Information about an additional on-line documentation for future up-to-date documentation is also available.

## 1 Introduction

The widely used off-line Lagrangian particle dispersion model (LPDM) FLEXPART (Stohl et al., 1998; Stohl et al., 2005; Piss0 et al., 2019) and its companion, the trajectory model FLEXTRA (Stohl et al., 1995; Stohl and Seibert, 1998), require meteorological data in GRIB format as input. A software package, flex\_extract, is provided to retrieve and prepare these data from the Meteorological Archival and Retrieval System (MARS) of the European Centre for Medium-Range Weather Forecasts (ECMWF) to run FLEXPART. Because of specific requirements of FLEXPART and FLEXTRA and the variations between the various ECMWF products, this is a complex task.

After the retrieval of the meteorological fields, flex\_extract calculates, if necessary, the vertical velocity in the native coordinate system of ECMWF's Integrated Forecast System (IFS), the so-called hybrid coordinate (Simmons and Burridge, 1981); furthermore, it calculates approximate instantaneous fluxes from the accumulated flux data provided by the IFS (precipitation

25 and surface fluxes of momentum and energy). It also takes care of packaging and naming the fields as expected by FLEXPART and FLEXTRA. The retrieval software is an integral part of the FLEXPART / FLEXTRA modelling system which is needed by users who apply the main branch based on the ECMWF meteorological fields (Pisso et al., 2019).

Flex\_extract is an open-source software package with a history starting in 2003 which has undergone adaptations and extensions ever since. After the release of version 7.0.2, which was very specific as it could retrieve data only from a subset of ECMWF's products, the demand for additional data sources and to adapt to new versions of ECMWF's software packages used arose. Unfortunately, the existing code was not very flexible and thus difficult to maintain and expand. User friendliness was insufficient, as knowledge about flex\_extract's driving parameters, the various ECMWF data sets, and their interaction was expected from users; with the increasing popularity of the FLEXPART model, improvements were necessary also in this respect. One of the priorities was to enable the extraction of fields from the reanalysis data sets ERA5 and CERA-20C. Additionally, the need for retrieving ensemble members in combination with forecast products arose. A recently developed new algorithm for disaggregation of the precipitation fields (Hittmeir et al., 2018) to improve the wet deposition calculation in FLEXPART should also be considered. With respect to ECMWF software packages on which flex\_extract depends a package called ecCodes replaced GRIB-API for decoding and encoding GRIB messages.

Recently, ECMWF opened the access to selected reanalysis data sets for non-member-state users, so-called public users from anywhere in the world, while previously only users with a member-state account could access the data. Along with this change, two new web interfaces (ECMWF's Web API and the Copernicus Data Service [CDS] Web API) were introduced, which allow to download data without direct access to ECMWF servers. This required a further adaptation, so that flex\_extract can now be used also on a local host in combination with these APIs for both member-state and public users.

All these developments led to the new and totally revised version 7.1 of flex\_extract introduced in this software description paper. It constitutes a more significant change of the code base than one might expect from the version number increment. The code was modularised in order to implement software quality standards and as a prerequisite of the extension of the functionality. A more comprehensive set of test cases was developed, the documentation was significantly enhanced with more details. A big step forward was thus achieved in terms of user friendliness.

This paper contains the first documentation of flex\_extract published in open literature and is valid for the – currently latest – version 7.1.2.

## 1.1 FLEXPART and FLEXTRA

The FLEXible PARTicle model (FLEXPART) is one of the most widely used Lagrangian particle dispersion models (LPDM) for multi-scale atmospheric transport studies (Stohl et al., 1998; Stohl et al., 2005; Pisso et al., 2019) with a world-wide user base. It is an open-source model under the GNU General Public Licence (GPL) Version 3. As an off-line model, it requires meteorological fields (analysed or forecast) as input. Such data are available from numerical weather prediction (NWP) models and thus several model branches have been created for input from different models (Pisso et al., 2019). The main branch of the FLEXPART model is able to use data from the ECMWF's IFS and the US National Centers for Environmental Prediction's (NCEP) Global Forecast System (GFS). The software package flex\_extract supports the extraction of ECMWF/IFS

data, considered to be the most accurate data source, as ECMWF is one of the leading global weather forecast centres and provides data on model-level and at high time resolution. As an LPDM, FLEXPART solves a Langevin equation for the trajectories of computational particles under the influence of turbulence (stochastic component) and quantifies changes to the trace substance mass or mixing ratio represented by these particles due to various processes.

Applications include a wide range of topics, such as air pollution, natural and man-made atmospheric radioactivity, stratosphere-troposphere exchange, and atmospheric water cycle studies and airflow patterns. With the domain-filling mode the entire atmosphere can be represented by particles representing an equal share of mass.

FLEXTRA is a model that calculates simple trajectories as a function of fields of the mean 3D wind (Stohl et al., 1995; Stohl and Seibert, 1998). FLEXPART is based on it and some code goes back to the same original routines from FLEXTRA. FLEXTRA ingests the same input fields in GRIB format as FLEXPART, thus it may be considered as a companion model. It is also free software and can be downloaded as well from the FLEXPART community web site.

Both FLEXTRA (v5.0) and FLEXPART (v9.02) can be used from within ECMWF's Metview software (ECMWF, 2019m).

## 1.2 The history of flex\_extract

When the FLEXTRA model was developed in the 1990s, one aim was to optimise its accuracy by avoiding unnecessary vertical interpolation. Therefore, it was implemented to directly use the three-dimensional wind fields on the IFS model levels rather than fields interpolated to pressure levels as most other off-line trajectory and particle dispersion models do (Stohl et al., 1995; Stohl and Seibert, 1998). This also solves the issue of the lower boundary conditions over topography (trajectories should not intersect the surface) in an optimum way. The IFS model uses a hybrid coordinate system, terrain-following near ground and approaching a pressure ( $p$ ) based coordinate towards the model top; the vertical coordinate is called  $\eta$  and thus the corresponding native vertical velocity is  $\dot{\eta}$ .

At that time, most ECMWF/IFS model fields were available on  $\eta$ -levels, however,  $\dot{\eta}$  was not routinely stored in the MARS archive. Thus, a pre-processing tool was needed to calculate accurate  $\dot{\eta}$  values from available fields. A second motivation was the need of a chemical transport model (POP model, see Wotawa et al. (1998)) coupled with FLEXTRA and later on FLEXPART for instantaneous surface fluxes (latent and sensible heat, surface stresses, precipitation) instead of accumulated values of these fluxes as stored in MARS.

When the Comprehensive Nuclear Test Ban Treaty Organization (CTBTO) started to use FLEXPART operationally, it became necessary to adapt the extraction software (consisting of Korn shell scripts and Fortran programmes for the numerically demanding calculation of  $\dot{\eta}$ ) such that it could be incorporated into ECMWF's automatic data dissemination system. This became the first numbered version of flex\_extract, v1, released in 2003. In version 2 (2006), it became possible to extract sub-regions of the globe and the Fortran code was parallelised with OpenMP. In Version 3, the option to use  $\dot{\eta}$  from MARS, which became available for some forecast products from 2008 on, was introduced. Version 4 was needed to adapt the package to the then new GRIB2 standard for meteorological fields. Versions 5 and 6 (2013) where adaptations to allow for higher horizontal resolutions and additional data sources, e. g. global reanalysis data. At this time, the Korn shell scripts had become quite complicated and difficult to maintain.

In 2015, the demand was raised to retrieve fields from long-term forecasts, not only analyses and short-term forecasts. At this stage, it was decided to rewrite `flex_extract` in Python2. The Python part controls the program flow by preparing korn shell scripts which are then submitted to ECMWF batch queue to start `flex_extract` in batch mode. The Fortran program for the calculation of the vertical velocity, `calc_etadot` (previously also called `CONVERT2` or `preconvert`), was still used and called from the Python code. Version 7.0.3 allowed to retrieve CERA-20C and ERA5 data, and introduced local retrieval of MARS data through the ECMWF Web API. Version 7.0.4 enabled the retrieval of multiple ensemble members at a time and included bug fixes for the retrieval of ERA5 and CERA-20C data.

For the current version 7.1, the Python part was completely revised by refactoring and modularisation, and it was ported to Python3. Instead of ECMWF's `GRIB-API` for decoding and encoding GRIB messages, its successor `ecCodes` was utilised. The installation process has been simplified. In addition to the ECMWF Web API, also the new CDS API is supported. The disaggregation of precipitation data offers to alternatively use the new algorithm of Hittmeir et al. (2018) which maintains non-negativity and preserves the integral precipitation in each time interval. The Fortran part underwent some mostly cosmetic changes (source format, file names, messages, etc. and a minor bug fix) and an overhaul of the makefiles. The code quality of `flex_extract` was improved by adding a first set of unit tests and the introduction of regression tests. A new, detailed on-line documentation was created with Sphinx / FORD, hosted on the FLEXPART community web site [http://flexpart.eu/flex\\_extract](http://flexpart.eu/flex_extract).

### 1.3 Structure of the paper

Section 2 gives an overview of available ECMWF data sets and their accessibility for member-state and public user, respectively. The diversity of available data sets, possible combinations of parameter settings, and accessibility is a key piece of information for users. The code of `flex_extract` is described in Sect. 3. This is followed by considerations for application in Sect. 4, and the methods applied for the quality assurance in Sect. 5. The final remarks in Sect. 6 include information support options for users and plans for future development. The technical instructions for the installation and usage of the software package are outlined in the Appendix.

## 2 ECMWF data

The ECMWF produces reanalysis data sets and global numerical weather predictions in operational service to its supporting Member States. All data are available to the national meteorological services in the Member States and the Co-operating States. Some data sets are also publicly available (ECMWF, 2019a). The data are stored in GRIB or BUFR format in MARS (ECMWF, 2019b). The smallest addressable object is a meteorological field or an observation, grouped into logical entities such as “a forecast”. These entities can be addressed through meta data organised in a tree-like manner. The meteorological fields are archived in one of three spatial representations: spherical harmonics (mainly model level fields), Gaussian grid (mainly surface fields, but also some model level fields), or a regular latitude / longitude grid (ECMWF, 2019b).

## 2.1 Access to ECMWF

For the access to its MARS archive, ECMWF distinguishes two user groups: member-state and public users. Member-state  
125 users have the possibility to work directly on the ECMWF Member State Linux servers as well as via a Web Access Toolkit  
(ECaccess) through a Member State gateway server. This mode provides full access to the MARS archive. Nevertheless, there  
might be some limitations in user rights, particularly regarding current forecasts and ensemble forecasts. Member-state user  
accounts are granted by the Computing Representative of the corresponding Member State. Public users access the ECMWF  
public data sets directly from their local facilities, anywhere in the world. The main differences to the member-state users are  
130 the method of access – through a Web API – and the limited availability of data. Public users have to explicitly accept the  
licence for the data set to be retrieved. Member-state users may also access data via a Web API, without a gateway server, in  
the same way as public users. The only difference is that different MARS databases are utilised. Flex\_extract automatically  
chooses the correct ones.

Users can explore the availability of data in MARS via a web interface where they are guided through a stepwise selection of  
135 meta data. With this method, it is also possible to estimate the download size of a data set before actually retrieving it through  
flex\_extract. There is a web interface “MARS Catalogue” for member-state users<sup>1</sup> with the full content and an interface “Public  
data sets” for public users<sup>2</sup> with the subset of public data. The availability of data can also be checked by MARS commands  
on ECMWF servers. MARS commands<sup>3</sup> are used by flex\_extract to retrieve the data on ECMWF servers.

## 2.2 Data sets available through flex\_extract

140 ECMWF has a large variety of data sets varying in model physics, temporal and spatial resolution as well as forecast times.  
Only the subset of data which are most commonly used with FLEXPART can be retrieved through flex\_extract. The accessible  
data sets are:

1. The operational deterministic atmospheric forecast model (DET-FC), nowadays called atmospheric high-resolution fore-  
cast model (HRES),
- 145 2. the operational atmospheric ensemble forecast (ENS),
3. the ERA-Interim reanalysis,
4. the CERA-20C reanalysis, and
5. the ERA5 reanalysis.

Public users have access to the public version of ERA-Interim (Berrisford et al., 2011), CERA-20C (Laloyaux et al., 2018) and  
150 ERA5 (Hersbach et al., 2020) reanalysis.

---

<sup>1</sup><https://apps.ecmwf.int/mars-catalogue/>; Last accessed: 17.08.2019

<sup>2</sup><https://apps.ecmwf.int/datasets/>; Last accessed: 17.08.2019

<sup>3</sup><https://confluence.ecmwf.int/display/UDOC/MARS+command+and+request+syntax>; Last accessed: 17.08.2019

The retrievable data sets are identified by the key meta data listed in the “Identification” section of Table 1. The relevant data period for each data set is also listed. Furthermore, the table presents the available temporal and spatial resolution as well as the number of ensemble members (may change in the future for the operational data). The availability of  $\eta$  is important for the mode of preparing the vertical velocity fields (see Sect. 3.7) and is therefore marked for accessibility as well. With the current  
155 operational data, a temporal resolution of 1 h can be established with a well-selected mix of analysis and forecast fields (see Sect. 4). The horizontal grid type refers to the spatial representation. Table 4 provides the relationship between corresponding spectral, Gaussian and latitude / longitude grid resolutions.

In this paper, we collect the essential changes in forecast steps and spatial resolution since the first IFS release, as they need to be known for using flex\_extract. Table 2 lists the evolution of horizontal and vertical resolutions for all operational data  
160 sets. The evolution of the forecast steps and the introduction of additional forecast times in “DET-FC” and “ENS-CF” are summarised in Table 3.

The reanalysis data sets are naturally more homogeneous. Nevertheless, they all have their individual characteristics, making the selection process with flex\_extract complex. Table 1 provides an overview of the main differences in the reanalysis meta data. ERA-Interim has a 3-hourly resolution with an analysis and forecast field mix in the full access mode but only a 6-  
165 hourly resolution for public users. It lacks the  $\eta$  fields which makes the retrieval of ERA-Interim computationally demanding (Sect. 3.7). The ERA5 and CERA-20C reanalyses can be retrieved with 1 h resolution and include ensembles; however, ERA5 ensemble members are not yet retrievable with flex\_extract and therefore omitted in the tables. Even though the availability of 1-hourly analysis fields means that forecast fields are not required for most of the variables, accumulated fluxes are only available as forecasts. One should also pay attention to different forecast start times in both data sets and the complication  
170 implied by forecasts starting from 18 UTC as the date will change until the subsequent start time; see also Sect. 3.6.

With the establishment of the Copernicus Climate Change Service (C3S) in March 2019, a new channel for accessing ECMWF reanalysis data, most prominently ERA5 (Hersbach et al., 2020), has been opened. At the same time, access to this data set via the ECMWF Web API was cancelled. While access directly from ECMWF servers is not affected, in local retrieval modes now one has to submit requests to the Copernicus Climate Data Store (CDS), which uses another Web API  
175 called CDS API; in the background, this API retrieves the public data from dedicated web servers for faster and easier access. Unfortunately, only surface and pressure level data are available in CDS at the moment; this might change in the future. It is possible to pass the request for model levels to the MARS archive even through the CDS interface. This is done automatically since flex\_extract is configured to do this. However, experience shows that this access mode is very slow<sup>4</sup>, thus currently it is not recommend for member-state users.

### 180 3 Software description and methods

The flex\_extract software package allows to retrieve and prepare the meteorological input files from ECMWF for FLEXPART (and FLEXTRA) easily and in an automated fashion. The necessary meteorological parameters to be retrieved are predefined

---

<sup>4</sup><https://confluence.ecmwf.int/display/CKB/How+to+download+ERA5>; Last accessed: 22.06.2020

according to the requirements of FLEXPART and the characteristics of various data sets. The post-processing after retrieval for the calculations of the flux fields (Sect. 3.6) and the vertical velocity (Sect. 3.7) is also included.


185 The actions executed by `flex_extract` (also called “the software package” henceforth) depend on the user group (see Sect. 2.1), the location of execution, and the data to be retrieved. There are three possible locations of execution, namely the ECMWF Member State Linux servers, the Member State Gateway server, or a local host. As not all combinations are possible, a total of four different application modes results which are described in Sect. 3.1. Because of the dependencies of `flex_extract`, the respective application environments need to be prepared in different ways as described in Sect. 3.2. The software package  
190 comprises a Python part for the overall control of the processing, including the data extraction, a Fortran part for the calculation of the vertical velocity, korn-shell scripts for batch jobs to run on ECMWF servers, and bash shell scripts as a user-friendly interface to the Python code. Available settings and input files are described in Sect. 3.4. The output files are divided into temporary files (Sect. 3.8) which are usually deleted at the end and the final output files (Sect. 3.9) which serve as FLEXPART input. An overview of the program structure and the work flow together with an example is given in Sect. 3.3.

195 The structure of the `flex_extract` root directory is presented in Table 5; it is completely different than in previous versions. The installation script `setup.sh` is directly stored under the root directory together with basic information files. `Source` contains all Python and Fortran source files, each in a separate directory. `Flex_extract` works with template files, stored in `Templates`. The on-line documentation is included in `Documentation` so that it can also be read off-line. The actual work by users takes place in the `Run` directory. There are the `CONTROL_*` files in the `Control` directory, the korn shell job  
200 scripts in `Jobscripts` and, in the case of applying the local mode, also a `Workspace` directory where the retrieved GRIB files and final FLEXPART input files will be stored. The `ECMWF_ENV` file is only created for the remote and gateway mode; it contains the user credentials for ECMWF servers. The `run.sh` and `run_local.sh` scripts are the top-level scripts to start `flex_extract`. Like in the previous versions, users can also directly call the `submit.py` script. There is also a directory `For_developers` which contains the source files of the on-line documentation, source files for figures, and sheets for  
205 parameter definitions.

### 3.1 Application modes

Arising from the two user groups described in Sect. 2.1 and the three possible locations of application, three different user application modes are defined, namely “remote”, “gateway” and “local” mode. However, the local mode is further split in the “local member” and the “local public” mode. A summary of the necessary registration method per mode and user group is  
210 outlined in Table 6. An overview of locations and modes is sketched in Figure 1 and a definition is given in the following list:

**Remote (member)** Users work directly on ECMWF Linux Member State servers, such as `ecgate` or `cca/ccb`. The software will be installed and run in the users `$HOME` directory. Users do not need to install any of the additional library packages mentioned in Sect. 3.2 since ECMWF provides everything with an environment modules framework. `Flex_extract` takes care of loading the necessary modules.



**Figure 1.** Schematic overview of access methods to the ECMWF MARS archive implemented in `flex_extract`.

215 **Gateway (member)** This mode is recommended in the case a local Member State Gateway server is in place (ECMWF, 2019j) and the user has a member-state account. Job scripts would then be prepared locally (on the gateway server) and submitted to the ECMWF Linux Member State server via the ECMWF web access toolkit `ECaccess`. The actual data extraction and post-processing is then done at the ECMWF servers and the final data are, if selected, transferred back to the local gateway server. The installation script of `flex_extract` must be executed at the local gateway server. However,

220 this will install `flex_extract` in the users `$HOME` directory on the ECMWF server and some extra setup is done in the local gateway version. For instructions about establishing a gateway server, please consult ECMWF (2019j) directly. The necessary software environment has to be established before installing `flex_extract`.

**Local member** Member-state users work on their local machines which require a similar software environment as the one on ECMWF servers plus the provided Web API's as the interface for the MARS archive.

225 **Local public** Public users can work on their local machines, having fulfilled the software dependencies and having added the ECMWF Web API and the CDS API as the interfaces to the public MARS archive. In this case, a direct registration at ECMWF and CDS is necessary, and all users have to accept a specific licence agreement for each data set which is intended to be retrieved.

### 3.2 Software dependencies

230 Software required to run `flex_extract` depends on the application mode. Basic requirements for all application modes are listed in Table 7. The local mode requires in addition Python packages `ecmwf-api-client` and / or `cdsapi`, depending on the data set to be retrieved, to connect to the MARS archive as Table 6 shows. Users should make sure that all dependencies are satisfied before starting the installation. `Flex_extract` is tested only in a GNU/Linux environment, although it might be possible to use it also under other operating systems.



The work of `flex_extract` can be decomposed into the following three separate tasks:

1. Setting the parameters controlling the retrieval and the data set:

Reading of the `CONTROL` file, command-line arguments, and ECMWF user credential file (in the case of remote or gateway mode). Depending on the application mode, `flex_extract` prepares a job script which is sent to the ECMWF batch queue, or proceeds with the tasks 2 and 3.

2. Retrieve data from MARS:

MARS requests are created in an optimised way (jobs split with respect to time and parameters) and submitted. Retrieved data are arranged in separate GRIB files. If the parameter `REQUEST` was set to 1, the request is not submitted and only a file `mars_requests.csv` is created. If it is set to 2, this file is created in addition to retrieving the data.


3. Post-process retrieved data to create final FLEXPART input files:

After all data are retrieved, flux fields are disaggregated, and vertical velocity fields are calculated by the Fortran program `calc_etadot`. Finally, the GRIB fields are merged into a single GRIB file per time step with all the fields FLEXPART expects. Depending on the parameter settings, file transfers are initiated and temporary files deleted.

In task 1, the execution of the code depends on the application mode. In the case of remote or gateway mode (see also Fig. 2), the job script for the ECMWF batch system is prepared and submitted to the batch queue. The program finishes with a message to standard output. In the case of the *local* application mode, the work continues locally with tasks 2 and 3, as illustrated in Figure 3.

Figure 4 demonstrates the involved input files, execution scripts and connection methods as well as the locations where each step takes place.

The remote and gateway mode both create a job script using the command-line parameters and the content of the specified `CONTROL` file and then sent it to an ECMWF batch queue. In remote mode this happens on an EMCWF server while the gateway mode uses the local gateway server for the creation and submission of the job. As the job script is executed from whichever of the two modes, it creates the job environment (in particular, the working directory) and starts `submit.py` to retrieve and post-process the data. Note that this locally started instance of `submit.py` triggers the work flow of the local mode but uses the MARS client to extract the requested fields from the database. The final output files are sent to the local member-state gateway server only if the corresponding option was selected in the `CONTROL` file. When `flex_extract` is used on a local host and in local mode, fields are extracted from MARS using one of the Web API's (which sends HTTP requests to ECMWF/CDS) and are received by the local host without storage on ECMWF servers.



**Figure 2.** Flow diagram for the remote and gateway mode. A job script is created and submitted to the batch queue on an ECMWF server. The job script will then be executed on the ECMWF server to start flex\_extract again for retrieving and post-processing of the data. The branch indicated by `queue = None` refers to the work flow shown in Figure 3. Trapezoidal boxes mark standard output, simple rectangles mark the execution of sequential instructions, and the rectangles with a side border mark the execution of subroutines. The boxes in diamond form indicate decisions.

## 3.4 Input files

### 265 3.4.1 The `CONTROL` file

Flex\_extract needs a number of controlling parameters. They are initialised by flex\_extract with their default values and will be overwritten by the settings in the `CONTROL` file. Only those parameters which deviate from the default values have to be provided. It is necessary to understand these parameters and to set them to proper and consistent values. They are listed in Table 8 with their default values and a short description. More detailed information, hints about the conditions of settings, and possible value ranges are available in the supplemental material, partially in Sect. 4 and the on-line documentation.

Regarding the file content, the first string in each line is the parameter name, the following string(s) (separated by spaces) are the parameter values. The parameters may appear in any order, with one parameter per line. Comments can be added as lines beginning with #-sign, or after the parameter value. Some of these parameters can be overruled by command-line parameters provided at program call.

275 The naming convention is `CONTROL_<dataset>[.optionalIndications]`, where the `optionalIndications` is an optional string to provide further characteristics about the retrieval method or the data set. See Sect. 4 for more details and examples.

### 3.4.2 User credential file `ECMWF_ENV`

In the remote and gateway mode, flex\_extract sends job scripts to the batch system of an ECMWF server, thus it is necessary to provide the user and group name which are given in file `ECMWF_ENV`. Additionally, this file provides the name of the local member-state gateway server and the destination so that unattended file transfer<sup>5</sup> (`ectrans`) between ECMWF and member gateway servers can be used. The destination is the name of the so-called `ectrans` association; it has to exist on the local gateway server.

### 3.4.3 Template files

285 Some files are highly variable depending on the setting in the other input files. They are created during run time by using template files. The templates are listed in Table 10. Flex\_extract uses the Python package `genshi` to read the templates and substitute placeholder by values. These placeholders are marked by a leading \$ sign. In the case of the korn shell job scripts, where (environment) variables are used, the \$ sign needs to be escaped by an additional \$ sign. Usually, users do not have to change these files.

---

<sup>5</sup><https://confluence.ecmwf.int/display/ECAC/Unattended+file+transfer+-+ectrans>; Last accessed: 09.09.2019

**3.5.1 Installation**

The shell script `setup.sh`, which is located in the root directory of `flex_extract`, installs `flex_extract`. It defines the installation parameters which are defined in Table 9 and Table 11 and applies some plausibility checks before it calls the Python script `install.py`. The Python script does the installation depending on the selected application mode. In the case of remote and gateway mode, the `ECMWF_ENV` file is created, the job script template `submitjob.template` is prepared and stored in the `Templates` directory and the korn shell script for compiling the Fortran source code `compilejob.ksh` is created. After these preparations, a tar ball with the core content is created and copied to the target location (ECMWF server or local installation path). Next, the `compilejob.ksh` is submitted to the batch system of ECMWF servers via `ECaccess` commands, or just untar-ed at the local target location. It compiles the Fortran code, prepares the work environment at ECMWF servers and, in the case of remote/gateway mode, a log file is sent to the user's email address.

**3.5.2 Execution**

The shell script `run.sh` or `run_local.sh` starts the whole procedure by calling the Python script `submit.py` with predefined command-line arguments (see Table 12) from a user section. The Python script constitutes as the main entry point and controls the program flow including the call of the Fortran program. Some of the parameters in `run.sh` are only needed at the time of the program call, while others are also defined in the `CONTROL` file. In this case, the values in `run.sh` take precedence over those from the `CONTROL` file.

The `submit.py` script interprets the command-line arguments and, based on the input parameter `QUEUE`, it decides which application mode is active. In *local mode*, data are fully extracted and post-processed, while in the *remote* and *gateway mode*, a korn shell script called `job.ksh` is created from the template `submitjob.template` and submitted to the ECMWF batch system. In case of the gateway mode, this is done via the local gateway server. The job script sets necessary directives for the batch system, creates the run directory and the `CONTROL` file, sets some environment variables (such as the `CONTROL` file name) and executes `flex_extract`. The standard output is collected in a log file which will be sent to the users' email address in the end. The batch system settings are fixed and they differentiate between the `ecgate` and the `cca/ccb` server systems to load the necessary modules for the environment when submitted to the batch queue. The `ecgate` server has directives marked with `SBATCH`<sup>6</sup> for the SLURM workload manager, the high performance computers `cca` and `ccb` have `PBS`<sup>7</sup> comments for PBSpro. The software environment dependencies mentioned in Sect. 3.2 are fulfilled by loading the corresponding modules. It should not be changed without further testing.

<sup>6</sup><https://confluence.ecmwf.int/display/UDOC/Writing+SLURM+jobs>; Last accessed: 10.09.2019

<sup>7</sup><https://confluence.ecmwf.int/display/UDOC/Batch+environment%3A++PBS>; Last accessed: 10.09.2019

### 3.6 Disaggregation of aggregated flux data

FLEXPART interpolates meteorological input data linearly to the position of computational particles in time and space (Stohl et al., 1998; Stohl et al., 2005). This method requires point values in the discrete input fields. However, flux data from ECMWF (as listed in Table 13) represent cell integrals and are accumulated over a time interval which depends on the data set. A pre-processing scheme is therefore applied to convert the accumulated values to point values valid at the same times as the main input fields while conserving the integral quantity with FLEXPART's linear interpolation.

The first step is to de-accumulate the fields in time so that each value represents an integral in  $(x, y, t)$ -space. Afterwards, a disaggregation scheme is applied. While the horizontal cell values are simply ascribed to the cell centre, with respect to time, a more complex procedure is needed because the final values should correspond to the same time as the other variables. In order to be able to carry out the disaggregation, additional flux data are retrieved automatically for one day before and one day after the period specified. Note that these additional data are temporary and used only for disaggregation within flex\_extract. They are not contained in the final FLEXPART input files. The flux disaggregation produces files named `fluxYYYYMMDDHH`, where YYYYMMDDHH is the date. Note that the first and last two flux files do not contain any data. Note that for operational retrievals which use the `BASETIME` parameter, forecast fluxes are only available until `BASETIME`, so that interpolation is not possible in the last two time intervals. This is the reason why setting `BASETIME` is not recommended for regular on-demand retrievals.

#### 3.6.1 Disaggregation of precipitation in older versions

In versions 7.0.x and before, a relatively simple method was applied to process the precipitation fields, consistent with the linear temporal interpolation applied in FLEXPART for all variables. At first, the accumulated values are divided by the number of hours (i.e., 3 or 6). For the disaggregation, precipitation sums of four adjacent time intervals  $(p_a, p_b, p_c, p_d)$  are used to generate the new instantaneous precipitation (disaggregated) value  $p$  which is output at the central point of the four adjacent time intervals:

$$p_{ac} = \begin{cases} 0.5 p_b & \text{for } p_a + p_c = 0 \\ \frac{p_b p_c}{p_a + p_c} & \text{for } p_a + p_c > 0 \end{cases} \quad (1)$$

$$p_{bd} = \begin{cases} 0.5 p_c & \text{for } p_b + p_d = 0 \\ \frac{p_b p_c}{p_b + p_d} & \text{for } p_b + p_d > 0 \end{cases} \quad (2)$$

$$p = p_{ac} + p_{bd} \quad (3)$$

The values  $p_{ac}$  and  $p_{bd}$  are temporary variables. The new precipitation value  $p$  constitute the de-accumulated time series used later in the linear interpolation scheme of FLEXPART. If one of the four original time intervals has a negative value, it is set to 0 prior to the calculation. Unfortunately, this algorithm does not conserve the precipitation within the interval under consideration, negatively impacting FLEXPART results as discussed by Hittmeir et al. (2018) and illustrated in Figure 5.

Horizontally, precipitation is given as cell averages. The cell midpoints coincide with the grid points at which other variables are given, which is an important difference to the temporal dimension. FLEXPART uses bilinear interpolation horizontally.

### 3.6.2 Disaggregation for precipitation in version 7.1

350 Due to the shortcomings described above, a new algorithm was developed by Hittmeir et al. (2018). In order to achieve the desired properties (Hittmeir et al., 2018, p. 2513), a linear formulation with two additional supporting points within each interval is used. The current version of flex\_extract implements this algorithm for the temporal dimension. Figure 6 shows how these requirements are fulfilled in the new algorithm for the simple case presented in Figure 5.

Flex\_extract allows to choose between the old and the new disaggregation method for precipitation. In the latter case, the  
 355 two additional sub-grid points are added in the output files. They are identified by the parameter STEP which is 0 for the original time at the left boundary of the interval, and, respectively, 1 and 2 for the two new sub-grid points. Filenames do not change. Current FLEXPART versions can not properly handle this input files generated with the new disaggregation scheme; they would use the third field (second additional sub-grid point in time), which would be worse than using the current method. The next minor version of FLEXPART to be released shall support the new scheme.

### 360 3.6.3 Disaggregation for the other flux fields

The accumulated values for the other fluxes are first divided by the number of hours, and then interpolated to the times of the major fields. The algorithm was designed to conserve the integrals of the fluxes within each time interval when reconstructed with a cubic polynomial. It uses the integrated values  $F$  during four adjacent time intervals ( $F_0, F_1, F_2, F_3$ ) to generate a new, disaggregated point value  $F$  which is output at the central point of the four adjacent time intervals:

$$365 \quad F = -\frac{1}{12}F_0 + \frac{7}{12}F_1 + \frac{7}{12}F_2 - \frac{1}{12}F_3 \quad (4)$$

Note that a cubic interpolation was never implemented in FLEXPART. We therefore plan to replace this scheme by an adaption of the scheme used for precipitation, adapted to the situation where both positive and negative values are possible.

### 3.7 Preparation of vertical velocity

An accurate representation of the vertical velocity is a key component for atmospheric transport models. One of the consider-  
 370 ations for the design of FLEXTRA was to work entirely in the native coordinate system of ECMWF’s IFS model to minimise interpolation errors. This meant that the same hybrid  $\eta$  coordinate (terrain-following near ground, approaching pressure levels towards the model top) would be used, which implied to use the corresponding native vertical velocity (“*etador*”)

$$\dot{\eta} = \frac{d\eta}{dt} \quad (5)$$

rather than the more commonly used ordinary vertical velocity in a simple  $z$ -system (units of  $\text{m s}^{-1}$ ) or the vertical motion  $\omega$   
 375 of pressure-based systems (unit  $\text{Pa s}^{-1}$ ). For reasons that we can’t reconstruct, however, FLEXTRA did not use  $\dot{\eta}$  strictly, but

rather a quantity

$$\dot{\eta}_p = \frac{d\eta}{dt} \frac{\partial p}{\partial \eta} \quad (6)$$

which obviously has units of  $\text{Pa s}^{-1}$ . The code calls this quantity *etapoint*, not to be confused with *etadot*. Even though in FLEXPART this concept had to be abandoned in favour of a terrain-following  $z$ -system to allow a correct implementation of the Langevin equation for turbulent motion, FLEXTRA and FLEXPART share the same requirement for the vertical motion with respect to their input. Over many years, ECMWF would store only the post-processed pressure vertical velocity  $\omega = dp/dt$ . Transforming this back to  $\dot{\eta}$ , with approximations and interpolations involved in both operations, leads to vertical velocities that do not fulfill continuity. Therefore,  $\dot{\eta}$  was reconstructed from the fields of divergence using the continuity equation, integrated from the model top downward as described in Simmons and Burridge (1981). In the IFS model, dynamical variables are horizontally discretised by spherical harmonics. It is best to do this on the reduced Gaussian grid that is used in IFS when a grid-point representation is required.

In September 2008, ECMWF started to archive the model's native vertical velocity fields ( $\dot{\eta}$ ) for the operational analyses and forecasts. This allowed `flex_extract` to skip the cumbersome reconstruction and directly use this parameter. The amount of data that needs to be extracted from MARS, the CPU time and the memory requirements are all reduced substantially. The ERA5 and CERA-20C reanalyses also provide  $\dot{\eta}$ . Thus, even though it is possible to use the old method on new data sets, there is no reason to do so and it would be a waste of resources. It is, however, still kept in `flex_extract` to allow extraction of data from the older data sets, in particular ERA-Interim. In the following, the two methods are briefly characterised.

### 3.7.1 Reconstruction of the vertical velocity using the continuity equation

The most accurate algorithm for the reconstruction of the native vertical velocity requires the extraction of the horizontal divergence fields and the logarithm of the surface pressure in spectral representation (and thus always global, regardless of the final domain), their transformation to the reduced Gaussian grid (introduced by Ritchie et al. (1995)), on which the continuity equation is solved, a transformation back to the spectral space, and finally the evaluation on the latitude-longitude grid desired by users. Especially for high spectral resolution, this is a compute- and memory-intensive process that also takes time, even when making use of OpenMP parallelisation. Larger data sets can only be treated on the supercomputer (`cca/ccb`) but not on `ecgate`. The code for these calculations is written in Fortran90.

Alternatively, data can be extracted from MARS immediately on the latitude-longitude grid for the domain desired, and the continuity equation is then solved on this grid, but this method is not as accurate as the calculations on the Gaussian grid, particularly for higher spatial resolutions.

### 3.7.2 Preparation of the vertical velocity using archived $\dot{\eta}$

If the vertical velocity is available in MARS, it only needs to be multiplied with  $\partial p / \partial \eta$ . In the `flex_extract` version discussed here, this is done by the Fortran program whose functionality is described below.

### 3.7.3 Short description of the functionality of the `calc_etadot` code

A dedicated working directory is used where all input and output files are kept. Currently, the files have names of the form `fort.xx` where `xx` is some number.

410 The control file steering the code is `fort.4` and has the form of a Fortran namelist. An overview of the options set by this namelist is contained in Table 14. The control file is prepared automatically by the Python code, but some of these parameters appear also as input to the Python part. Note that the selection of the method for obtaining  $\dot{\eta}$  follows the logic laid out in Table 15.

All other input files are data in GRIB format that were retrieved from MARS. The code is using dynamic memory allocation  
415 and thus does not need to be recompiled for different data sets.

The code is provided with a set of makefiles. The standard version assumes a typical GNU/Linux environment with the `gfortran` compiler and the required libraries: `OpenMP` for parallelisation which is included in the `gcc` compiler package (`libgomp`), `ecCodes` for handling GRIB files, `EMOSLIB` for transformation between the various representations of fields. Note that the latter two typically require also so-called developer packages containing the Fortran module files. One may  
420 substitute `ecCodes` by its predecessor `GRIB_API`, if `ecCodes` is not available. It is assumed that these libraries have been installed as a package from the distribution and thus are at their standard locations and compatible with the `gfortran` compiler (if not, the makefile library and include paths need to be adapted). There is one makefile called `makefile_fast` with optimisation that is used for production. In addition, there is `makefile_debug` which is optimised for debugging. There are also makefiles for the ECMWF servers `cca/ccb` and `ecgate`.

425 If the program finishes successfully, the last line written to standard output is `SUCCESSFULLY FINISHED calc_etadot: CONGRATULATIONS` which is useful for automated checking the success of the run. The output file into which the fields of  $\dot{\eta}_p$  and the other three-dimensional variables (temperature, specific humidity,  $u$  and  $v$  components of the wind – not the recently introduced cloud water variable) are combined is `fort.15`; it is a GRIB file.

The code also foresees options for certain checks where different forms of the vertical velocity are obtained, statistically  
430 compared, and also written out (see Table 14). These options were used for quality control in the development process and should not normally be activated by users.

Currently, the code also unifies the three-dimensional fields extracted from MARS and stored in separate GRIB files with the calculated vertical velocity by writing out all fields into a single GRIB file; later this is unified with the 2D fields and the new 3D parameters such as cloud water and written out into a final single GRIB file as required by `FLEXTRA` and `FLEXPART`.

### 435 3.8 Temporary output files

These temporary output files are usually deleted after a successful data extraction. They are only kept in debugging mode, which is the case if the `DEBUG` parameter is set to true.



### 3.8.1 MARS GRIB files

All extracted meteorological fields from MARS are in GRIB format and stored in files ending with `.grb`. MARS requests  
440 are split in an optimised way to reduce idle times and considering the limit of data transfer per request. The output from each  
request is stored in one GRIB file whose name is defined as `<field_type><grid_type><temporal_property>  
<level_type>.<date>.<ppid>.<pid>.grb`. The field type can be analysis (AN), forecast (FC), 4d variational anal-  
ysis (4V), validation forecast (CV), control forecast (CF) and perturbed forecast (PF). The grid type can be spherical harmonics  
(SH), Gaussian grid (GG), output grid (OG) (typically lat/lon) or orography (`_OROLSM`) while the temporal property distin-  
445 guishes between an instantaneous field (`_`) or an accumulated field (`_acc`). Level types can be model (ML) or surface level  
(SL) and the date is specified in the format `YYYYMMDDHH`. The last two placeholders are the process number of the parent  
process of submitted script (ppid) and the process number of the submitted script (pid). The process IDs are incorporated so  
that the GRIB files can be addressed properly in the post-processing.

### 3.8.2 MARS request file

450 This file contains a list of the MARS requests from one `flex_extract` run, with one request per line. This is an optional file users  
are able to create in addition to full extraction; it can also be created without actually extracting the data which is useful for test  
purposes. Each request consist of the following parameters whose meaning is explained in Table 8, and in more detail in the  
supplemental material or are self-explanatory: request number, accuracy, area, dataset, date, expver, Gaussian, grid, levelist,  
levtype, marsclass (alias class), number, param, repres, resol, step, stream, target, time and type. The parameters Gaussian  
455 (defines whether the field is regular or a reduced Gaussian grid), levtype (distinguishes between model levels and surface level)  
and repres (defines the grid type – SH, GG, OG) are internal parameters not defined as any available input parameter.

### 3.8.3 Index file

The index file is called `date_time_stepRange.idx`. It contains indices pointing to specific GRIB messages from one or  
more GRIB files so Python can easily loop over these messages. The messages are selected with a predefined composition of  
460 GRIB keywords.

### 3.8.4 Files with forecast vertical flux data

The flux files, in the format `flux<date>[.N<xxx>][.<xxx>]`, contain the de-accumulated and disaggregated flux fields  
which are listed in Table 13. The files are created per time step with the date being in the format `YYYYMMDDHH`. The optional  
block `[.N<xxx>]` marks the ensemble forecast, where `<xxx>` is the ensemble member number. The second optional block  
465 `[.<xxx>]` marks a long forecast (see Sec. 3.9.2) with `<xxx>` being the forecast step.

Note that, in the case of the new disaggregation method for precipitation, two new sub-intervals are added in between each  
original time interval. They are identified by the forecast step parameter `STEP` which is 0 for the original time interval and 1  
or 2 for the two new intervals respectively.

### 3.8.5 `fort.*` files

470 There are a number of input files for the `calc_etadot` Fortran program named `fort.xx`, where `xx` is the number which defines the meteorological fields stored in these files. They are generated by the Python part of `flex_extract` by just splitting the meteorological fields for a unique time step from the `*.grb` files. Table 16 explains the numbers and the corresponding content. Some of the fields are optional and are retrieved only with specific settings, for example the divergence is retrieved only if  $\eta$  is not available in MARS, and the total cloud water content is an optional field for FLEXPART v10 and newer. The  
475 output of `calc_etadot` is file `fort.15`.

## 3.9 Final output – FLEXPART input files

The final output files are the FLEXPART input files containing the meteorological information. FLEXPART expects one file with all relevant fields per time step. Table 17 and 18 list all of the meteorological fields that `flex_extract` retrieves and FLEXPART expects. The naming of these files depends on the extracted data. In the following sections we describe the  
480 differences and how the filenames are built.

### 3.9.1 Standard output files

The standard file names have the format `<prefix>YYMMDDHH`, where the `<prefix>` is by default defined as `EN` and can be re-defined in the `CONTROL` file. Each file contains all fields on all selected levels on a latitude-longitude grid as needed by FLEXPART. There is one file per time step and `YYMMDDHH` indicate the date and hour for which the fields are contained in the  
485 file. Analysis and forecast times with their corresponding forecast steps are summarized to the actual times. If not otherwise stated, model-level fields are in GRIB2 format and surface fields in GRIB1. When CERA-20C data are retrieved, the date format is changed to `YYYYMMDDHH`.

### 3.9.2 Output files for long forecasts

For a long forecast, where only forecast fields are retrieved for more than 23 hours, a different naming scheme has to be applied  
490 to avoid collisions of time steps for forecasts of more than one day. This case is defined as long forecast mode and file names are defined as `<prefix>YYMMDD.HH.<FORECAST_STEP>`. The `<prefix>` is, as in the standard output files, `EN` by default and can be re-defined in the `CONTROL` file. In this case, the date format `YYMMDD` does not include the hour. The `HH` represents the starting time (base time) of the forecast. The `FORECAST_STEP` is a 3-digit number which represents the forecast step in hours.

### 495 3.9.3 Output files for ensemble predictions

If `flex_extract` retrieves ensemble members, multiple fields result for each meteorological variable (the ensemble members) at a single time step. They are distinguished by the GRIB parameter `NUMBER`. All fields of one ensemble member are collected

together in a single file per time step. The standard filenames are supplemented by the letter N for “number” and the ensemble member number in a 3-digit format such as <prefix>YYMMDDHH.N<ENSEMBLE\_MEMBER>.

### 500 3.9.4 Additional fields with new precipitation disaggregation

The new disaggregation method for precipitation fields produces two additional fields for each time step and precipitation type. They contain the sub-grid points in the corresponding original time intervals as described above in Sect. 3.6.2. The two additional fields are marked with the STEP parameter in the GRIB messages, are set to “1” and “2”, respectively. The output filenames do not change in this case.

## 505 4 Considerations for application

As in earlier versions of the software package, it is still possible to directly start flex\_extract with the Python script submit.py. An overview of its current command-line arguments is available through ./submit.py --help. Please note that when flex\_extract is started in local mode, the parameter INPUTPATH in the run\_local.sh script must be set, so that each retrieval uses a unique directory to avoid mixing of data files.

510 There are two more entry points into flex\_extract which can be used for debugging; they are described here for the sake of completeness: the Python scripts getMARSdata.py and prepare\_flexpart.py. In the standard way of running flex\_extract, they are both imported as modules (as shown in Fig. 3), but they can also be used as executable programs. The script getMARSdata.py controls the extraction of ECMWF data, while prepare\_flexpart.py controls the post-processing. It may happen that the procedure terminates unexpectedly during the post-processing due to time limits on ECMWF  
515 servers. In this case, the prepare\_flexpart.py script can be used to redo the complete post-processing, bypassing the need to retrieve the data from MARS again.

### 4.1 Example CONTROL files

The file CONTROL.documentation provides a collection of the available parameters grouped in sections together with their default values. Users can start from this file to define their own setup, or use one of the example CONTROL files as a template (in  
520 flex\_extract\_v7.1/Run/Control/). For each data set (see Sect. 2.2), a basic example CONTROL file is provided with some additional variations in, for example, horizontal and temporal resolution, field type, method for vertical velocity or duration of forecasts. The variations are specified at the end of the file name (CONTROL\_<dataset>[.optionalIndications]) as an optional string.

The usage section in the on-line documentation provides more details on how to set the CONTROL file parameters for  
525 specific applications. For example, CONTROL filenames which end with .public are for public users. They have the specific parameter DATASET for CERA-20C and ERA-Interim data sets to identify the public version in MARS. For ERA5, this parameter is not needed, and thus public users may use any ERA5 file for extraction. For the atmospheric high resolution data sets, indicated by OD, the optional string contains information of the stream (OPER, ENFO, ELDA), the field type of forecasts

(FC, CF, CV, PF, 4V), the method for extracting the vertical velocity (eta or gauss), and other aspects such as long forecasts  
530 (36hours), operational half-day retrievals (basetime or twicedaily), temporal resolution (1hourly or 3hourly) or  
different horizontal resolutions with global vs. limited-area domains (highres).

## 4.2 Changes in CONTROL file parameters in comparison to previous versions

With version 7.1, all CONTROL file parameters are initialised with default values. Thus, only those which need to be changed  
to identify the data set to be retrieved have to be set in the CONTROL file. In earlier versions, each parameter name contained  
535 the leading string M\_; this was removed for version 7.1, but is still accepted for compatibility. The grid resolution had to be  
provided in 1/1000 of a degree before, while now it can be provided also as a decimal number. Flex\_extract is able to identify  
the correct setting of the GRID parameter in combination with the domain-specific settings.

It is now also possible to reduce the number of data values for the combination of TYPE, TIME and STEP parameters to the  
actual temporal resolution. Previous versions expected to have 24 values per parameter, one for each hour of the day, even if  
540 only 3-hourly data would be requested as shown in the following example:

```
DTIME 3
TYPE AN AN AN AN ... AN AN AN AN
TIME 00 01 02 03 ... 20 21 22 23
STEP 00 00 00 00 ... 00 00 00 00
```

545 The more intuitive solution of providing the data for the time steps to be retrieved leads, in this example, to eight data values  
per parameter for a 3-hourly retrieval:

```
DTIME 3
TYPE AN AN AN AN AN AN AN AN
TIME 00 03 06 09 12 15 18 21
550 STEP 00 00 00 00 00 00 00 00
```

or four values for a 6-hourly retrieval

```
DTIME 6
TYPE AN AN AN AN
TIME 00 06 12 18
555 STEP 00 00 00 00
```

The only necessity is a consistent setting of the DTIME parameter which defines the temporal resolution. For backward com-  
patibility, DTIME may be coarser than the number of temporal points provided in TYPE, TIME and STEP, but not finer.

With this version of flex\_extract, it is possible to retrieve data sets with analysis fields at every hour (such as ERA5  
and CERA-20C); therefore, it was necessary to introduce new parameters related to flux fields defining the forecast type

560 (ACCTYPE), time (ACCTIME) and step (ACCMAXSTEP) specifically for the flux fields (accumulated quantities). For daily ERA5 retrievals, which need up to 12 h forecasts twice a day for the flux fields, these parameters would be:

```
ACCTYPE FC
ACCTIME 06/18
ACCMAXSTEP 12
```

565 Several new parameters were introduced which work as switches. Among the more important ones are REQUEST in order to write the settings in the MARS requests to an output file `mars_requests.csv`, and CWC to trigger the additional retrieval of cloud liquid and ice water content. DOUBLEELDA can be used to double the number of ensemble members if only 25 members are available from the ELDA stream. These additional members are calculated by subtracting from each existing ensemble member twice the amount of the difference between the ensemble member and the control run. To distinguish between the old  
570 and new precipitation disaggregation scheme, the switch parameter RRINT was introduced. Setting it to 1 indicates that the new scheme is used; 0 selects the old scheme

### 4.3 Scientific considerations

First of all, users should be aware of the different nature of operational and reanalysis data sets (see Table 1). Operational data are available since the start of ECMWF's operational forecasts, and are influenced by frequent changes in the IFS model,  
575 for example with respect to model physics and resolution. Reanalysis data sets were created using a single IFS model version throughout the whole period covered. More precisely, the CERA-20C data set (with 91 vertical levels, 1.25° horizontal and 3 h temporal resolution) has a lower resolution but covers a very long period (from 1901 to 2010) and will thus be suitable for certain climate applications. The ERA-Interim data set (with 60 vertical levels, a medium resolution of 0.75° horizontally and 3 h temporally) was the standard ECMWF reanalysis until recently, but without  $\dot{\eta}$  having been stored in the MARS archive,  
580 making retrievals computationally demanding as it needs to be reconstructed from the horizontal winds through the continuity equation. The new ERA5 data set has the highest resolution (0.25° horizontally and 1 h temporally, 137 vertical model levels) and includes  $\dot{\eta}$ . Users are encouraged to use ERA5 data rather than the ERA-Interim data set (production ended in August 2019). In addition to its better resolution, ERA5 covers a longer period than ERA-Interim, provides uncertainty estimates with a 10-member ensemble data assimilation, and uses a newer IFS model version (ECMWF, 2019).

585 With respect to the relation between temporal and spatial resolution, it is important to consider the use in FLEXPART and their influence on numerical errors. It is not useful to apply high horizontal resolution in combination with, for example, 6-hourly temporal resolution as in such a case, small fast-moving structures are resolved in space, but their movement will not be properly represented. Interpolation will not let the structures move, but rather jump from their position at time  $t$  to that at time  $t + 6$  h if the displacement between two subsequent times where fields are available is comparable to or larger than their  
590 characteristic width along to the phase speed. Users can orient themselves looking at the spatial and temporal resolutions at which ECMWF provides reanalysis data, and the sample CONTROL files.

On the other hand, one has to keep in mind the requirements of the FLEXPART application. For a climatological study on global scales, a horizontal resolution of  $0.5^\circ$  or  $1^\circ$  could be a reasonable choice, whereas tracking point releases in complex terrain would call for the best available resolution.

595 Attention should also be paid to the model topography and the land-sea mask. Due to limited resolution, a coastal site with a given geographical coordinate could be over water in the model. Then it might be better to shift the coordinates of a release or receptor point in FLEXPART slightly. Another aspect is that the smoothed representation of the topography could mean that the model topography is above or below the real height of a site. It is therefore important to select the proper kind of  $z$  coordinate in the FLEXPART RELEASES file. As a compromise, one can place a release location at a height between real  
600 and model topography (for mountain sites which are usually lower in the model topography than in reality). In such cases, it is strongly recommended to retrieve the model topography and land-sea mask manually and investigate them carefully before deciding on the FLEXPART set-up details, or even before retrieving the full meteorological data set, as one might come to the conclusion that one with better resolution should be used.

The vertical levels used in FLEXPART follow a hybrid  $\eta$  coordinate system. This is much more efficient than pure pressure  
605 levels since hybrid  $\eta$  coordinates follow the terrain near ground and approach pressure levels towards the model top. This allows to easily fulfil the lower boundary condition of a flow parallel to the surface whereas pressure levels do not follow the terrain (Stohl et al., 2001), while still at higher levels of the atmosphere, where the flows are close to horizontal, strong vertical motions derived from coordinate transformation are avoided. It also allows better to assign a higher vertical resolution to the lowest part of the atmosphere. ECMWF data sets either directly provide the  $\eta$  variable (set ETA and DPDETA to 1, see  
610 CONTROL files with eta in their names), or include the data needed to reconstruct it (set GAUSS to 1, see CONTROL files with gauss in their names) accurately. This is a big advantage of ECMWF data compared to other data sources, most notably the NCEP model data, which are publicly available only on pressure levels.

Attention should be paid to the number of vertical model levels to be extracted and used in FLEXPART, as the computational cost of the FLEXPART `verttransform` subroutine (reading and preparing meteorological input) increases with the  
615 third power of the number of vertical levels. Thus, only data that are really needed for the application (e.g. troposphere, or troposphere and lower stratosphere) should be extracted. File `CONTROL_OD.OPER.FC.eta.highres.reducedlev`, for example, retrieves a limited domain with high horizontal ( $0.2^\circ$ ) and 1-hourly temporal resolution with  $\eta$  levels up to, approximately, 100 hPa by setting `LEVELIST` to `60/TO/137`.

Operational data sets and ERA-Interim have analysis fields at 6- or 12-hour intervals (00, (06), 12 and (18) UTC) only.  
620 The gaps inbetween can be filled with forecast fields. Mixing analysis and forecast fields should be done by considering at which time steps the differences between two IFS run segments will be the smallest. For example, using all four analysis fields together with forecasts starting at 00 and 12 UTC would lead to undesired changes between 05, 06, and 07 UTC and 17, 18, and 19 UTC. This should be avoided by using only 00 and 12 UTC analysis fields and the forecast fields for +1 to +11 hours for the forecasts starting at times 00 and 12 UTC, respectively (note that forecasts from the intermediate analyses at 06 and 18  
625 UTC are not archived). See file `CONTROL_OD.OPER.FC.eta.global` for an example.

## 5 Quality assurance

To assure a certain quality of a piece of software, testing is at least as important as developing the code itself. Adding new functionalities requires to develop new tests to identify possible bugs, or to show that the code works under specified conditions. As a consequence, output from the tests conducted with the preceding version can be used to verify that there are no unexpected side effects. This is called regression testing (Beizer, 1990; Spillner, 2012). As the functionality of the software changes, tests need to be updated or expanded as well. For this flex\_extract version, code refactoring was at the core of the development, and a number of regression tests were developed for that. In addition, a first set of unit tests (Sect. 5.1), which also serve as a kind of regression test, have been developed within the refactoring process as they are the established best-practice in software engineering to investigate small code blocks. Furthermore, we defined test cases to compare the outcome of two flex\_extract versions after three different stages of the retrieval process: (1) the MARS requests prepared (Sect. 5.2), (2) the vertical velocity obtained with the different options of calculation (Sect. 5.4), and (3) the final output files in GRIB format (Sect. 5.3). In addition, generic tests were performed by applying flex\_extract with predefined CONTROL files (Sect. 5.5) which are distributed with the software package to serve as examples for the typical applications. Finally, some code metrics were determined to track quantitative quality aspects of the code. The combination of all of these tests establishes a sustainable testing environment, which will benefit the future development process. The testing environment is not directly relevant for users of flex\_extract.

### 5.1 Unit tests

Unit tests are used to test the smallest pieces of code (single code blocks) independently to identify a potential lack of functional specification (Beizer, 1990). Applying unit tests does not guarantee error-free software, rather it limits the likelihood of errors. Once the tests are written, they serve also as a kind of documentation and to protect against alteration of the functional behaviour by future code changes (Wolff, 2014). In this sense, they are also a kind of regression test.

For the current version of flex\_extract, we prepared a first set of unit tests for functions which were designed or partly refactored to be testable code blocks. Our intention is to increase the number of unit tests in the future, and to further refactor some still rather complex functions into smaller ones (see also Sect. 5.6 or the supplemental material for identifying complex functions).

### 5.2 Regression testing for MARS requests

The parameters in the MARS requests produced by flex\_extract are a key component of the extraction process. Flex\_extract v7.1 contains a test to compare the content of MARS requests as produced by two versions. It checks whether the number of columns (parameters) in the request files (see Sect. 3.8.2) is unchanged, whether the number of requests is equal, and whether the content of the request is identical (except for the desired differences and the environment-dependent data such as paths).

The MARS request files for the current version in use are generated automatically at runtime without actually retrieving the data, while the files for the reference version have to be in place before. Since the MARS request files are grouped by version and are saved, the number of reference data sets will grow with each new version.

### 5.3 Regression testing for GRIB files

The final product of `flex_extract`, the FLEXPART input files in GRIB format (see Sect. 3.9), should be equal between the previous and the current version, apart from the new or modified features. Since there is always a possibility to have tiny (insignificant) deviations in the actual field values when retrieving at different points in time (changes in the environment, library versions, computational uncertainties, etc.), the focus of this test lies on the files themselves and the GRIB message headers which should not be different. Future improvements may also test for value differences considering a significance threshold.

A regression test was created which compares the GRIB files produced by two versions with respect to the number of files produced, the file names, the number of GRIB messages per file, the content of the GRIB messages header, and statistical parameters for the data themselves. If differences are reported, the developer has to judge whether they are expected or indicate a problem.

### 5.4 Functionality and performance tests for the Fortran code

Regression tests were set up to reflect the three possibilities for obtaining the vertical velocity  $\dot{\eta}$  listed in Table 15. In addition to a basic test for each, enriched tests are implemented where all checks and additional outputs are activated (names with appended `all`). These tests use a pre-specified small domain ( $10^\circ \times 10^\circ$ , 11 levels) and low spectral resolution (T159) and thus run quite fast. As high spectral resolution and a large domain may pose specific problems, and as it will be relevant to watch the run times, additional high-resolution tests have been created for the `gauss` and `etadot` cases with a domain covering the northern hemisphere and all 137 vertical levels. The `gausshigh` test uses a grid spacing of  $0.25^\circ$  and the corresponding spectral resolution of T799; the `etadot` case uses  $0.1^\circ$  and T1279.

### 5.5 Generic test using predefined CONTROL files

`Flex_extract` comes with a set of `CONTROL` files, which can be found in the `flex_extract_v7.1/Run/Control` directory; executing `flex_extract` with each of them constitutes a generic test which ensures that the data extraction works for all typical applications.

### 5.6 Code Metrics

Metrics for the maintainability and complexity of code as well for the documentation are a useful tool for developers who should aim at maintaining or reaching good scores in these metrics. For the Python code of `flex_extract`, a number of metrics were calculated for the previous version 7.0.4 and the current version 7.1. This section summarizes the metrics and their main findings. More details can be found in the supplemental material.

Basic metrics, taken from Lacchia (2019) and calculated with the Python package `radon` (Lacchia, 2019), are

- the total number of lines of code (`LOC`),



- the number of logical lines of code (`LLOC`),
- the number of source lines of code (`SLOC`),
- 690 – the number of (single) comment lines (`comments`),
- the number of lines in multi-line comment strings (`multi`), and
- the number of blank lines (`blank`),

with the following relation between these numbers:

$$\text{LOC} = \text{SLOC} + \text{multi} + \text{comment} + \text{blank}. \quad (7)$$

695 The comparison shown in Table 19 indicates a significant increase not only in the logical lines of code, but even more in `comment` and `multi`, mostly representing an improvement of in-line documentation by splitting large code blocks into smaller ones, each with a new `docstring`. A so-called `docstring` is a specific multi-line comment for the documentation of functions, methods and classes, describing their input and return values, which can be read by tools for automatic generation of a separate documentation. The re-factorisation of code blocks, additional code for new features, and compliance with certain  
700 code style rules (e.g., maximum length of lines), about 1000 lines of pure code were added. The ratio of comment lines (`multi` + `comment`) to source-code lines (`SLOC`) grew from 20 % to 117 %.

A further metric for code quality is the so-called *cyclomatic complexity* (CC), also called the McCabe metric (Sneed et al., 2010). It is equal to the number of linearly independent paths through the control flow graph of the code or the number of decisions plus one. A lower CC score indicates a lower complexity which is deemed an advantage. Table 20 gives an overview  
705 of the rank definitions. Regarding code testing, CC provides a lower-bound number of how many test cases (unit tests) are necessary to provide complete path coverage (Beizer, 1990).

In general, it is said that the score should be less or equal 10, corresponding to rank A and B. From the statistical point of view, only 10.3 % of `flex_extract` version 7.1 code blocks have higher complexity, while in version 7.0.4 this was the case for 30.8 %.

710 The mean cyclomatic complexity of all code blocks in the new Python code is 5.74 (B); for those blocks with C to F, it is 21 (C). In version 7.0.4, the corresponding numbers are 13 (C) and 31.86 (E), indicating a substantial improvement. For example, the class `ControlFile` was improved significantly, as well as the class renamed from `EIFlexpart` to `EcFlexpart`. On the other hand, the class method `deacc_fluxes` became more complex in version 7.1. This is mainly due to two new features, ensemble retrieval and the new disaggregation. Nevertheless, the overall code complexity was reduced.

715 Another software metric is the maintainability index (MI), where values 0 – 9 indicate low maintainability, 10 – 19 medium, and 20 – 100 high maintainability. The index is calculated for a complete Python file. Both Python versions have in general highly maintainable Python files except `FlexpartTools.py` in version 7.0.4 with an MI score of 0.0 and `EcFlexpart.py` in version 7.1 with an MI score of 10.79.

Additionally, we used a source code quality checker program called `pylint` (Thénault, 2001) which indicates how well the Python style guide PEP8 (van Rossum et al., 2001) is followed. This tool provides an overall rating index with a maximum value of 10. According to this tool, `flex_extract` version 7.0.4 has a rating of -8.77 and version 7.1 a rating of 9.09. This shows a massive improvement in following the official style guide.

## 6 Final remarks and outlook

### 6.1 Conclusions

This paper describes the software package `flex_extract` v7.1, which retrieves meteorological fields from the ECMWF IFS model and prepares them for the use in the Lagrangian particle dispersion model FLEXPART. The package was initially developed in the 1990s and underwent various developments to adapt to changes in the ECMWF environment and the data set characteristics. In the past two years, ECMWF introduced considerable changes in its software environment for retrieval, reading and accessing data and also released new data sets. This necessitated a substantial upgrade of `flex_extract` to adapt to these changes. Moreover, the user community had new requirements for data retrievals which were considered in this version. In the development process, substantial refactoring was carried out, the number of retrievable data sets was increased, user-friendliness was improved, current ECMWF software packages considered, an on-line documentation was built, and a first set of test cases for future regression testing was created. Furthermore, a recently developed and improved disaggregation method for precipitation fields was implemented as an option.

The number of groups using FLEXPART grew substantially over the past decade and with the new opportunity of publicly available reanalysis data sets there will likely be even more users interested in trying out and applying FLEXPART for their research. Alongside with this reference paper, the newly established git repository on the FLEXPART community web site <https://flexpart.eu> and the on-line documentation should assist all these users with up-to-date information about changes, releases of new versions, installation and usage including a documentation useful for future developers.

### 6.2 Support

FLEXPART has a community web site <http://flexpart.eu>, where `flex_extract` as a pre-processor has its own sub page<sup>8</sup>. The web site features a ticket system to report issues or submit feature requests. The tickets can be viewed by anyone; to create a ticket, registration<sup>9</sup> is necessary. There is also a mailing list for discussion among FLEXPART / FLEXTRA users and with developers, where questions may be asked or experiences be shared, including pre- and post-processing issues. Announcements for all FLEXPART users, such as new releases, are distributed through the list as well. Future contributions to the code are welcome; for granting permission of write access to the git repository, communication via email or ticket is necessary.

---

<sup>8</sup><https://www.flexpart.eu/wiki/FpInputMetEcmwf>; Last accessed: 17.08.2019

<sup>9</sup><https://www.flexpart.eu/wiki/RegisteredUser>; Last accessed: 17.08.2019

### 6.3 Future work

In its current status, the on-line documentation provides a basic reference. In the future, more examples should be provided, including answers to typical user questions and workarounds for known problems. Information about updates and new releases will also be implemented in this documentation.

It is also intended to provide for the optional retrieval of meteorological fields needed as input (initial and boundary conditions) for the WRF model to support the FLEXPART-WRF community.

The unification of the various three-dimensional fields into a single file shall be removed from the Fortran code as this is a simple task that can be fulfilled more efficiently and transparently with `ecCodes` command-line tools.

The ERA5 reanalysis has ensemble members stored in the *enda* stream, but the flux data have a different accumulation period and therefore are not yet retrievable. It is planned to allow the retrieval of these ensemble members in the future. Up to now, it is possible to set `flex_extract` to retrieve fields on the reduced Gaussian grid. This should be extended to include the octahedral reduced Gaussian grid.

The hybrid vertical velocity  $\dot{\eta}$  is now stored not only for the operational forecasts but also for the new reanalyses, thus the need to calculate it is diminishing. In future versions of `flex_extract`, `calc_etadot` will probably only be called if  $\dot{\eta}$  really needs to be calculated, not just for multiplying it with  $\partial p / \partial \eta$  as this can be done with sufficient efficiency in Python.

The `flex_extract` software package is currently provided as a compressed tar file. In the future, a package shall be made available to be installed as a system package for certain GNU/Linux distributions. In this case, only user-specific data will need to reside in the user directories.

*Code and data availability.* `Flex_extract` is a code package consisting of Python scripts, shell scripts and a Fortran program; it is open software distributed under a Creative Commons (CC-BY-4.0) licence. The latest version of the code (currently 7.1.2) is available through the `flex_extract` project webpage (<https://www.flexpart.eu/wiki/FpInputMetEcmwf>; Last accessed: 09.07.2020) which is part of the FLEXPART community web site and contains links to the tarball and the git repository; the on-line documentation is also hosted there ([https://www.flexpart.eu/flex\\_extract/](https://www.flexpart.eu/flex_extract/); Last accessed: 09.07.2020).

The exact version at the time of manuscript submission is archived on Phaidra (<https://phaidra.univie.ac.at/view/o:1070149>, DOI:10.25365/phaidra.130), the permanent secure storage of the University of Vienna.

The software package comes with a number of test cases which should be used by developers in the future. Some tests need additional reference data which have to be downloaded separately from the project web site. The following open-source libraries have to be available in addition to the libraries mentioned in the installation section in order to run the `flex_extract` test cases: `numpy/scipy` (Walt et al., 2011), `pandas` (McKinney, 2010), `xarray` (Hoyer and Hamman, 2017), `pytest` (Krekel, 2019), `mock` (Foord and the mock team, 2019). For the generation of the on-line documentation, the Python package `sphinx` (Brandl, 2019) is required, and for the documentation of the Fortran code, `FORD`<sup>10</sup>.

---

<sup>10</sup><http://fortranwiki.org/fortran/show/FORD>, accessed 20 Dec 2019

The current version 7.1 of flex\_extract was developed under GNU/Linux and was tested only on this platform. Application under other operating systems may be possible, but without supported by the developers.

## 780 **Appendix A: Installation instructions**

First of all, download the release version from the FLEXPART community web site. Alternatively, if git is installed on the target machine, you may clone the latest version of the master branch from the git repository on the community web site.

```
git clone --single-branch --branch master
https://www.flexpart.eu/gitmob/flex_extract
```

785 Currently, flex\_extract was only tested for a GNU/Linux environment. The installation process depends on the user group (see Sect. 2.1) and the application mode (see Sect. 3.1). One should first decide for the modes and then follow the compact instructions in the corresponding subsections. Shell scripts and Python code snippets mentioned in the Appendix can be found in the directory Testing/Installation/ after unpacking the tarball. For more details see the instructions in the on-line documentation.

## 790 **A1 Registration and licences**

Table 6 summarizes which registration is required. Follow the given links from the literature to the registration web sites (or footnotes).

A separate licence has to be accepted for each ECMWF public data set, regardless of the user group. For the ERA-Interim and CERA-20C datasets this can be done at the web site for “Available ECMWF Public Datasets”<sup>11</sup>. Log in and follow the  
795 licence links on the right side for each data set and accept it. For the ERA5 data set this has to be done at the “Climate Data Store (CDS) web site”<sup>12</sup>. Log in and select, on the left panel, product type “Reanalysis” for finding ERA5 data sets. Then follow any link with ERA5 to the full data set record, click on tab “Download data” and scroll down. There is a section “Terms of use” where the “Accept terms” button has to be clicked. The licences for member-state users are accepted by the user when receiving a so-called “Token”, which generates new passwords for each log in.

## 800 **A2 System prerequisites**

### **Remote mode**

ECMWF servers provide all required libraries (see Table 7) via an environment modules framework. Flex\_extract takes care of loading the right modules at runtime.

---

<sup>11</sup><https://confluence.ecmwf.int/display/WEBAPI/Available+ECMWF+Public+Datasets>; Last accessed: 11.11.2019

<sup>12</sup><https://cds.climate.copernicus.eu/cdsapp#!/search?type=dataset>; Last accessed: 11.11.2019

## Gateway mode

805 In this mode, access to the ECMWF computing and archiving facilities is enabled through an `ECaccess` gateway server on a local member state server. The `ECaccess` framework is necessary to interactively submit jobs to the ECMWF batch system and to transfer files between ECMWF and local gateway server. As a consequence, a member state gateway server has to be established<sup>13</sup> and a so-called association<sup>14</sup> has to be created to use the `ECaccess` file transfer service `ectrans`. The next step is to create an `ECaccess` certificate to authorise the file transfers and job submissions. This certificate has to  
810 be renewed periodically (every 7 days). The certificate is created by executing the command `ecaccess-certificate-create` on the command-line of the local gateway server and the user is prompted for the ECMWF member-state user name and a password (generated by a token).

```
$ ecaccess-certificate-create
Please enter your user-id: example_username
815 Your passcode: ***
```

Additional dependencies on the local gateway server are `Python3` and the Python packages `NumPy` and `genshi`. Use the package management system of your Linux distribution which requires admin rights. The installation was tested under GNU/Linux Debian buster and Ubuntu 18.04 Bionic Beaver. The following installation instructions refer to a Debian-based system and use `apt-get` as package manager; of course, other package managers (e.g. `aptitude`), or other GNU/Linux  
820 distributions can be used as well.

```
apt-get install python3
apt-get install python3-genshi
apt-get install python3-numpy
```

## Local mode

825 For the local mode, all software dependencies listed in Sect. 3.2 have to be provided. The installation process is the same for the member-state and public access modes. Use the package management system of your Linux distribution (requires admin rights) to establish the dependencies if not already available. Note that for the Python version of `ecCodes`, a version 2.13.0 or higher is necessary.

```
830 apt-get install python3
apt-get install python3-eccodes
apt-get install python3-genshi
apt-get install python3-numpy
apt-get install gfortran
apt-get install fftw3-dev
835 apt-get install libeccodes-dev
apt-get install libemos-dev
```

---

<sup>13</sup><https://confluence.ecmwf.int/display/ECAC/ECaccess+Home>; Last accessed: 31.10.2019

<sup>14</sup><https://confluence.ecmwf.int/download/attachments/45759146/ECaccess.pdf> see page 17 ff. for instructions; Last accessed: 28.10.2019

As currently the CDS and ECMWF API packages are not available as Debian packages, they need to be installed outside the Debian (Ubuntu etc.) package management system. The CDS API (`cdsapi`) is required for ERA5 data and the ECMWF Web API (`ecmwf-api-client`) for all other public datasets. The recommended way is to use the Python package management

840 system `pip`:

```
apt-get install pip
pip install cdsapi
pip install ecmwf-api-client
```

Note that if you would like to use Anaconda Python we recommend you follow the installation instructions of Anaconda  
845 Python Installation for Linux and then install the `ecCodes` package from conda with:

```
conda install conda-forge::python-eccodes
```

Both user groups have to provide keys with their credentials for the Web APIs in their home directory. Therefore, follow these instructions:

**ECMWF Web API** Go to MARS access web site<sup>15</sup> and log in with your credentials. Afterwards, on this site in section “Install  
850 ECMWF KEY” the key for the ECMWF Web API should be listed. Please follow the instructions in this section under  
1 (save the key in a file `.ecmwfapirc` in your home directory).

**CDS API** Go to CDS API registration<sup>16</sup> and register there too. Log in at the `cdsapi` web site and follow the instructions at  
section “Install the CDS API key” to save your credentials in a `.cdsapirc` file in your home directory.

Since a single retrieval run of `flex_extract` can take a while, it is recommended to do some basic tests for the local access  
855 method to identify problems with the Web APIs early on. A very simple test retrieval for both Web APIs are enough to be sure  
that everything works. For the ECMWF Web API and as a member-state user please use this piece of Python code:

```
from ecmwfapi import ECMWFService

server = ECMWFService('mars')

860 server.retrieve({
    'stream'      : "oper",
    'levtype'     : "sfc",
    'param'       : "165.128/166.128/167.128",
865 'dataset'     : "interim",
    'step'        : "0",
    'grid'        : "0.75/0.75",
    'time'        : "00/06/12/18",
    'date'        : "2014-07-01/to/2014-07-31",
870 'type'        : "an",
    'class'       : "ei",
    'target'      : "download_erainterim_ecmwfapi.grib"
})
```

---

<sup>15</sup><https://confluence.ecmwf.int/display/WEBAPI/Access+MARS>; Last accessed: 20.10.2019

<sup>16</sup><https://cds.climate.copernicus.eu/api-how-to>; Last accessed: 25.10.2019

For the ECMWF Web API and as a public user please use that piece of Python code:

```
875 from ecmwfapi import ECMWFDataServer

server = ECMWFDataServer()

server.retrieve({
880 'stream'      : "enda",
    'levtype'    : "sfc",
    'param'      : "165.128/166.128/167.128",
    'dataset'    : "cera20c",
    'step'       : "0",
885 'grid'       : "1./1.",
    'time'       : "00/06/12/18",
    'date'       : "2000-07-01/to/2000-07-31",
    'type'       : "an",
    'class'      : "ep",
890 'target'     : "download_cera20c_ecmwfapi.grib"
})
```

Extraction of ERA5 data via CDS API might take time as currently, at the time of publication, there is a high demand for ERA5 data. Therefore, as a simple test for the API, just retrieve pressure-level data (even if that is NOT what we need for FLEXPART), as they are stored on disk and don't need to be retrieved from MARS (which is the time-consuming action):

895 Please use this piece of Python code (both user groups) to retrieve a small sample of ERA5 pressure levels:

```
import cdsapi

c = cdsapi.Client()

900 c.retrieve("reanalysis-era5-pressure-levels",
    {
        "variable": "temperature",
        "pressure_level": "1000",
        "product_type": "reanalysis",
905 "year": "2008",
        "month": "01",
        "day": "01",
        "time": "12:00",
        "format": "grib"
910 },
    "download_cdsapi.grib")
```

An example for retrieving ERA5 data from MARS is shown below and can be tested if the code from above worked.

```
import cdsapi

915 c = cdsapi.Client()

c.retrieve('reanalysis-era5-complete',
    {
        'class'    : 'ea',
```

```

920 'expver' : '1',
    'stream' : 'oper',
    'type' : 'fc',
    'step' : '3/to/12/by/3',
    'param' : '130.128',
925 'levtype' : 'ml',
    'levelist': '135/to/137',
    'date' : '2013-01-01',
    'time' : '06/18',
    'area' : '50/-5/40/5',
930 'grid' : '1.0/1.0',
    'format' : 'grib',
    }, 'download_era5_cdsapi.grib')

```

### A3 Building flex\_extract

#### Remote mode

935 First, log in on one of the ECMWF servers, such as `ecgate` or `cca/ccb`. Second, copy the tarfile to the server, untar the `flex_extract` release tarball and change into the `flex_extract` root directory.

```

scp <localuser>@<localmachine.tld>:</path/to/tarfile> $HOME
cd $HOME
tar xvf flex_extract_vX.X.tar.gz
940 cd flex_extract_vX.X

```

Substitute the `<localuser>` and `<localmachine.tld>` placeholders with your local user name and the IP name or address of your local machine. Eventually, adapt the parameters (described in Table 11 and 9) in the `setup.sh` script and execute it. `Flex_extract` uses the email address connected to the user account to notify the user about successful or failed installation.

#### 945 Gateway mode

The actual execution of `flex_extract` with retrieval and preparation of the data will be run on ECMWF servers. The only difference is the preparation of the job script, which is done on the local gateway server and sent to ECMWF servers by the `ECaccess` services. Unpack the release tarball and change into its directory. Substitute `X.X` with the actual release version number.

```

950 tar xvf flex_extract_vX.X.tar.gz
    cd flex_extract_vX.X

```

Afterwards, prepare the `setup.sh` script by configuring its parameters (described in Table 11 and 9) and execute it. The `makefile` has to be selected according to the selection of the target, e.g. `ecgate` or `cca/ccb` servers. In this mode the `DESTINATION` and `GATEWAY` parameters have to be set to be able to use the `ectrans` service. A configuration job script is then sent to the

955 ECMWF batch queue and `flex_extract` uses the email address connected to the user account to notify the user about successful or failed installation.



## Local mode

Since `flex_extract` compiles the Fortran program `calc_etadot` during the installation process, a corresponding makefile has to be provided. `Flex_extract` comes with a prepared makefile for the `gfortran` (<https://gcc.gnu.org/fortran/>) compiler. The makefile assumes that `ecCodes` and `EMOSLIB` are installed as distribution packages. It is necessary to adapt the two parameters `ECCODES_INCLUDE_DIR` and `ECCODES_LIB` in these makefiles if other than standard paths are used. Therefore, if needed, prepare the Fortran makefile for your environment by starting from the makefile `makefile_fast` provided and edit the paths to point to the `ecCodes` library on your local machine. It can be found at `flex_extract_vX.X/Source/Fortran`, where `vX.X` should be substituted with the current version number. Eventually, adapt the command-line parameters (described in Table 9 and 11) in the `setup.sh` script in the root directory of `flex_extract` and execute it.

## A4 Installation test

The most common errors in applying `flex_extract` arise from wrong installation and settings regarding the libraries for the Fortran program. Therefore it is useful to do a simple test with a prepared minimal data set. The following instructions have to be executed on the local system for the local mode and on the ECMWF servers in the remote and gateway mode. From the `flex_extract` root directory change into the `Testing/Installation/Calc_etadot/` directory and execute the Fortran program by

```
cd Testing/Installation/Calc_etadot
# execute the Fortran program
../../../../Source/Fortran/calc_etadot
```

The installation was successful if you obtain on standard output:

```
STATISTICS:          98842.4598  98709.7359   5120.5385
STOP SUCCESSFULLY FINISHED calc_etadot: CONGRATULATIONS
```

Note that on ECMWF servers the `flex_extract` root directory is placed in the `$HOME` directory.

## Appendix B: Usage instructions

`Flex_extract` is a command-line tool which can be started by executing the `submit.py` script in the Python source directory or more preferably with an upstream shell script `run.sh` which calls the `submit.py` script with its corresponding command-line arguments. Therefore, the user should navigate to the `Run` directory, where the shell script is located.

```
cd <path-to-flex_extract_vX.X>/Run
```

with `X.X` as the placeholder for the version number. This directory contains all information necessary to run `flex_extract`. The only files which might need modifications by the user are the `run.sh` script and the selected `CONTROL` file within the `Control` directory. This directory contains a sample set of the current range of possible data set retrievals.

This section describes the basic steps to start a flex\_extract retrieval within the different modes based on an example. More details about the usage can be found in Sect. 4 and in the on-line documentation, especially specifics of different data sets and CONTROL file parameters.

990 For the first data retrieval it is recommended to use one of the example CONTROL files stored in the Control directory to avoid unnecessary problems. We recommend to extract CERA-20C data since they are usually not highly demanded and guarantee quick processing for the best testing experience. In the following, we will provide step-by-step instructions for all application modes to retrieve a single day (08 September 2000) from the CERA-20C dataset with 3-hourly temporal resolution and a small domain over Europe with 1° resolution, using CONTROL\_CERA[.public].

## 995 Remote and gateway modes

For member-state users it is recommended to use the remote or gateway mode, especially for more demanding tasks, to retrieve and post-process data on ECMWF machines and to transfer only the final output files to the local host. The only difference between both modes is the location where flex\_extract will be started from. In the remote mode we work directly on the ECMWF server, therefore login to the ECMWF server of your choice and change to the Run directory as shown above.

1000 Remember, at ECMWF servers flex\_extract is always installed in the \$HOME directory. Within the gateway mode, only a change into the Run directory of flex\_extract on the gateway server is necessary. Otherwise, the rest of the working steps are the same in both modes. Now, open the run.sh script and modify the parameter block marked in the file as shown below. The parameters are described in Table 12.

```
# -----
1005 # AVAILABLE COMMANDLINE ARGUMENTS TO SET
#
# THE USER HAS TO SPECIFY THESE PARAMETERS:

1010 QUEUE='ecgate'
START_DATE=None
END_DATE=None
DATE_CHUNK=None
JOB_CHUNK=3
BASETIME=None
1015 STEP=None
LEVELIST=None
AREA=None
INPUTDIR=None
OUTPUTDIR=None
1020 PP_ID=None
JOB_TEMPLATE='submitscript.template'
CONTROLFILE='CONTROL_CERA'
DEBUG=0
REQUEST=2
1025 PUBLIC=0
```

This would retrieve CERA-20C data on the ECMWF server `ecgate`. For the ECMWF `cca/ccb` servers, the parameter `QUEUE` has to be adapted. Since the `ectrans` parameter in the `CONTROL_CERA` file is set to 1 the resulting output files will be transferred to the local gateway into the path stored in the destination, provided that the destination was correctly set-up.

Please note that success of the submission of the `ectrans` command does not guarantee that the file transfer will succeed. It means only that the output file has been successfully submitted to the `ectrans` queueing system. One still has to check manually in the local directories or with `ECaccess` tools whether the files reached their final destination. The parameters listed in the `run.sh` script would overwrite existing settings from the `CONTROL` file.

Starting the retrieval process will be done by executing the script by `./run.sh`. `Flex_extract` will print some information about the job on standard output. If there is no error in the submission to the ECMWF server a message like this will be shown:

```
1035 ---- On-demand mode! ----
The job id is: 10627807
You should get an email per job with
    subject flex.hostname.pid
FLEX_EXTRACT JOB SCRIPT IS SUBMITTED!
```

Once submitted, the job status can be checked by using the command `ecaccess-job-list`. At the end of the job, the user should receive an email with a detailed protocol of what was done and if the job was successful.

In case the job failed, the subject will contain the keyword *ERROR!* and the job name. Then, the user can check the email or on ECMWF servers in the `$SCRATCH` directory for debugging information.

In the `$SCRATCH` directory on `ecgate` it is recommended to list the content with `ls -rthl` to list the most recent logs and temporary retrieval directories (usually `extractXXXXXX`, where `XXXXXX` is the process id). Under `extractXXXXXX` a copy of the `CONTROL` file is stored under the name `CONTROL`, the protocol is stored in the file `prot` and the temporary files as well as the resulting files are stored in a directory `work`. The original name of the `CONTROL` file can be found within this new file under parameter `controlfile`.

If the job was submitted to the High Performance Computer (HPC) (`QUEUE` is `cca` or `ccb`) you may login to the HPC and look into the directory `/scratch/ms/ECGID/ECUID/.ecaccess_do_not_remove` for job logs. The working directories are deleted after job failure and thus normally cannot be accessed.

If the resulting files can not be found in the destination path of the local gateway server, it can be checked if the files are still to be transferred to the local gateway server by using the command `ecaccess-ectrans-list`.

After this test retrieval was successful, feel free to try changing the `CONTROL` file parameters described in Table 8 and by selecting other `CONTROL` files. Please mind the considerations of application in Sect. 4.

## Local mode

Since this mode can be used by member-state and public users, we show an example for both user groups. Open the `run_local.sh` file and adapt the parameter block marked in the file as shown for the corresponding user group. The parameters are described in Table 12. Take this setting as a member-state user:

```
1060 # -----
# AVAILABLE COMMANDLINE ARGUMENTS TO SET
```

```

#
# THE USER HAS TO SPECIFY THESE PARAMETERS:
#
1065 QUEUE=''
    START_DATE=None
    END_DATE=None
    DATE_CHUNK=None
1070 JOB_CHUNK=None
    BASETIME=None
    STEP=None
    LEVELIST=None
    AREA=None
1075 INPUTDIR='./Workspace/CERA'
    OUTPUTDIR=None
    PP_ID=None
    JOB_TEMPLATE=''
    CONTROLFILE='CONTROL_CERA'
1080 DEBUG=0
    REQUEST=0
    PUBLIC=0

```

and take this setting as a public user:

```

# -----
1085 # AVAILABLE COMMANDLINE ARGUMENTS TO SET
#
# THE USER HAS TO SPECIFY THESE PARAMETERS:
#
1090 QUEUE=''
    START_DATE=None
    END_DATE=None
    DATE_CHUNK=None
    JOB_CHUNK=None
1095 BASETIME=None
    STEP=None
    LEVELIST=None
    AREA=None
    INPUTDIR='./Workspace/CERApblic'
1100 OUTPUTDIR=None
    PP_ID=None
    JOB_TEMPLATE=''
    CONTROLFILE='CONTROL_CERA.pblic'
1105 DEBUG=0
    REQUEST=0
    PUBLIC=1

```

The working location for this retrieval is set by the INPUTDIR parameter and will be the Workspace/CERA\* directory within the current Run directory. It is also the output directory since OUTPUTDIR was not set. This can be changed to whatever

path is preferred. The parameters listed in `run_local.sh` would overwrite existing settings in the `CONTROL` file. Starting  
1110 the retrieval process will be done by executing the script by `./run_local.sh`.

While a job submission on the local host is convenient and easy to monitor (on standard output), there are a few caveats with  
this option. There is a maximum size of 20 GB for single retrievals via ECMWF Web API. Normally this is not a problem but  
for global fields with T1279 resolution and hourly time steps the limit may already apply. If the retrieved MARS files are large  
but the resulting files are relatively small (small local domain, but large time period) then the retrieval to the local host may be  
1115 inefficient since all data must be transferred via the Internet. This scenario applies most notably if ETADOT has to be calculated  
via the continuity equation as this requires global fields even if the domain is local and small. In this case, job submission via  
`ecgate` might be a better choice. It really depends on the patterns used and also on the speed of the internet.

After this test retrieval was successful, feel free to try changing the `CONTROL` file parameters described in Table 8 and by  
selecting other `CONTROL` files. Please mind the considerations of application in Sect. 4.

1120 *Author contributions.* A. Philipp revised the complete software package (except for the Fortran part) and applied the necessary changes to  
keep it up-to-date with the ECMWF software environment. She coordinated and added new implementations and guided the evaluation. She  
wrote the on-line documentation as well as most of the manuscript.

L. Haimberger is the original author of the software package and provided the first implementation for the use of the ECMWF Web API and  
the retrieval of ensemble members. He participated in writing introductory and history parts as well as giving feedback on all other parts.

1125 P. Seibert revised the Fortran code and provided the Fortran code documentation and test cases, and wrote the respective section of the  
manuscript. She also gave feedback on all other parts, and contributed to editing the final manuscript version.

*Competing interests.* The authors declare that they have no conflict of interest.

*Acknowledgements.* Over the years, the development of `flex_extract` was partly funded by the CTBTO. We thank the ZAMG for providing  
1130 access to the ECMWF MARS archive and the hosting of the community web site. We would also like to thank the ECMWF user support for  
their assistance in converging the software environment to the current state and for their many publicly available code examples for working  
with GRIB files. Additionally, we thank Anne Fouilloux for an initial version of the Python routines. Moreover, we thank the users for their  
feedback and questions which made it possible to make progress in user friendliness, eliminate bugs and react on requirements.

## References

- 1135 Beizer, B.: Software Testing Techniques, Van Nostrand Reinhold, 2nd edn., 1990.
- Berrisford, P., Dee, D., Poli, P., Brugge, R., Fielding, M., Fuentes, M., Kållberg, P., Kobayashi, S., Uppala, S., and Simmons, A.: The ERA-Interim archive Version 2.0, ERA Report Series, Vol. 1, <https://www.ecmwf.int/node/8174>, 2011.
- Brandl, G.: Sphinx - Python Documentation Generator, <http://www.sphinx-doc.org/en/master/>, 2019.
- Buizza, R., Richardson, D. S., and Palmer, T. N.: Benefits of increased resolution in the ECMWF ensemble system and comparison with poor-man's ensembles, Quarterly Journal of the Royal Meteorological Society, 129, 1269–1288, <https://doi.org/10.1256/qj.02.92>, <https://rmets.onlinelibrary.wiley.com/doi/abs/10.1256/qj.02.92>, 2003.
- Copernicus: How to use the CDS API, <https://cds.climate.copernicus.eu/api-how-to>, 2019.
- ECMWF: ERA-Interim: What is the spatial reference, <https://confluence.ecmwf.int/display/CKB/ERA-Interim%3A+What+is+the+spatial+reference>, 2016a.
- 1145 ECMWF: ERA5: What is the spatial reference, <https://confluence.ecmwf.int/display/CKB/ERA5%3A+What+is+the+spatial+reference>, 2016b.
- ECMWF: OpenIFS: Horizontal Resolution Configurations, <https://confluence.ecmwf.int/display/OIFS/4.2+OpenIFS%3A+Horizontal+Resolution+Configurations>, 2017.
- ECMWF: ECMWF, <https://www.ecmwf.int>, [Online; 05.08.2019], 2019a.
- 1150 ECMWF: MARS User Documentation, <https://software.ecmwf.int/wiki/display/UDOC/MARS+user+documentation>, [Online; 05.08.2019], 2019b.
- ECMWF: Forecasting system upgrade set to improve global weather forecasts, <https://www.ecmwf.int/en/about/media-centre/news/2019/forecasting-system-upgrade-set-improve-global-weather-forecasts>, 2019c.
- ECMWF: Data spatial coordinate systems, <https://www.ecmwf.int/en/forecasts/documentation-and-support/data-spatial-coordinate-systems>, accessed: August 26, 2019, 2019d.
- 1155 ECMWF: MARS Catalogue, <https://apps.ecmwf.int/mars-catalogue/>, 2019e.
- ECMWF: Changes in ECMWF model, <https://www.ecmwf.int/en/forecasts/documentation-and-support/changes-ecmwf-model>, 2019f.
- ECMWF: IFS Documentation, <https://www.ecmwf.int/en/publications/ifs-documentation>, 2019g.
- ECMWF: ERA5 data documentation, <https://confluence.ecmwf.int/display/CKB/ERA5+data+documentation>, 2019h.
- 1160 ECMWF: Parameter database, <https://apps.ecmwf.int/codes/grib/param-db>, 2019i.
- ECMWF: Ecaccess concepts, <https://confluence.ecmwf.int/display/ECAC/Ecaccess+concepts>, 2019j.
- ECMWF: ECMWF Web API Home, <https://confluence.ecmwf.int/display/WEBAPI/ECMWF+Web+API+Home>, 2019k.
- ECMWF: What are the changes from ERA-Interim to ERA5?, 2019l.
- ECMWF: Tutorials, <https://confluence.ecmwf.int/display/METV/Tutorials>, [Online; 18.12.2019], 2019m.
- 1165 Foord, M. and the mock team: Mock object library, <https://mock.readthedocs.io/en/latest/>, 2019.
- Hersbach, H., Bell, B., Berrisford, P., Hirahara, S., Horányi, A., Muñoz-Sabater, J., Nicolas, J., Peubey, C., Radu, R., Schepers, D., Simmons, A., Soci, C., Abdalla, S., Abellan, X., Balsamo, G., Bechtold, P., Biavati, G., Bidlot, J., Bonavita, M., Chiara, G. D., Dahlgren, P., Dee, D., Diamantakis, M., Dragani, R., Flemming, J., Forbes, R., Fuentes, M., Geer, A., Haimberger, L., Healy, S., Hogan, R. J., Hólm, E., Janisková, M., Keeley, S., Laloyaux, P., Lopez, P., Radnoti, G., de Rosnay, P., Rozum, I., Vamborg, F., Villaume, S., and Thépaut, J.-N.: The ERA5 Global Reanalysis, Quart. J. Roy. Met. Soc., submitted, 2020.
- 1170

- Hittmeir, S., Philipp, A., and Seibert, P.: A conservative reconstruction scheme for the interpolation of extensive quantities in the Lagrangian particle dispersion model FLEXPART, *Geoscientific Model Development*, 11, 2503–2523, <https://doi.org/10.5194/gmd-11-2503-2018>, <https://www.geosci-model-dev.net/11/2503/2018/>, 2018.
- Hoyer, S. and Hamman, J.: xarray: N-D labeled arrays and datasets in Python, *Journal of Open Research Software*, 5, <https://doi.org/10.5334/jors.148>, <http://doi.org/10.5334/jors.148>, 2017.
- Krekel, H.: pytest Documentation, Online, <https://buildmedia.readthedocs.org/media/pdf/pytest/latest/pytest.pdf>, 2019.
- Lacchia, M.: radon 4.0.0 - Project description, <https://pypi.org/project/radon/>, 2019.
- Laloyaux, P., Balmaseda, M., Dee, D., Mogensen, K., and Janssen, P.: A coupled data assimilation system for climate reanalysis, *Quarterly Journal of the Royal Meteorological Society*, 142, 65–78, 2016.
- 1180 Laloyaux, P., de Boisseson, E., Balmaseda, M., Bidlot, J.-R., Broennimann, S., Buizza, R., Dalhgren, P., Dee, D., Haimberger, L., Hersbach, H., Kosaka, Y., Martin, M., Poli, P., Rayner, N., Rustemeier, E., and Schepers, D.: CERA-20C: A Coupled Reanalysis of the Twentieth Century, *Journal of Advances in Modeling Earth Systems*, 10, 1172–1195, <https://doi.org/10.1029/2018MS001273>, <https://agupubs.onlinelibrary.wiley.com/doi/abs/10.1029/2018MS001273>, 2018.
- McKinney, W.: Data Structures for Statistical Computing in Python, in: *Proceedings of the 9th Python in Science Conference*, edited by van der Walt, S. and Millman, J., pp. 51 – 56, 2010.
- 1185 Palmer, T. N., Barkmeijer, J., Buizza, R., and Petrolia, T.: The ECMWF Ensemble Prediction System, *Meteorological Applications*, 4, 301–304, <https://doi.org/10.1017/S1350482797000649>, 1997.
- Pisso, I., Sollum, E., Grythe, H., Kristiansen, N., Cassiani, M., Eckhardt, S., Arnold, D., Morton, D., Thompson, R. L., Groot Zwaafink, C. D., Evangelou, N., Sodemann, H., Haimberger, L., Henne, S., Brunner, D., Burkhart, J. F., Fouilloux, A., Brioude, J., Philipp, A., Seibert, P., and Stohl, A.: The Lagrangian particle dispersion model FLEXPART version 10.3, *Geoscientific Model Development Discussions*, 2019, 1–67, <https://doi.org/10.5194/gmd-2018-333>, <https://www.geosci-model-dev-discuss.net/gmd-2018-333/>, 2019.
- 1190 Ritchie, H., Temperton, C., Simmons, A., Hortal, M., Davies, T., Dent, D., and Hamrud, M.: Implementation of the Semi-Lagrangian Method in a High-Resolution Version of the ECMWF Forecast Model, *Mon. Weather Rev.*, 123, 489–514, 1995.
- Simmons, A. J. and Burridge, D. M.: An Energy and Angular-Momentum Conserving Vertical Finite-Difference Scheme and Hybrid Vertical Coordinates, *Mon. Weather Rev.*, 109, 758–766, 1981.
- 1195 Sneed, H. M., Seidl, R., and Baumgartner, M.: *Software in Zahlen*, Hanser, 2010.
- Spillner, Andreas; Linz, T.: *Basiswissen Softwaretest*, dpunkt, 5th edn., 2012.
- Stohl, A. and Seibert, P.: Accuracy of trajectories as determined from the conservation of meteorological tracers, *Q. J. Roy. Meteor. Soc.*, 125, 1465–1584, 1998.
- 1200 Stohl, A., Wotawa, G., Seibert, P., and Kromp-Kolb, H.: Interpolation errors in wind fields as a function of spatial and temporal resolution and their impact on different types of kinematic trajectories, *J. Appl. Meteorol.*, 34, 2149–2165, 1995.
- Stohl, A., Hittenberger, M., and Wotawa, G.: Validation of the Lagrangian particle dispersion model FLEXPART against large-scale tracer experiment data, *Atmospheric Environment*, 32, 4245–4264, [https://doi.org/10.1016/S1352-2310\(98\)00184-8](https://doi.org/10.1016/S1352-2310(98)00184-8), 1998.
- Stohl, A., Haimberger, L., Scheele, M., and Wernli, H.: An intercomparison of results from three trajectory models, *Meteorol. Applications*, 8, 127–135, 2001.
- 1205 Stohl, A., Forster, C., Frank, A., Seibert, P., and Wotawa, G.: Technical note: The Lagrangian particle dispersion model FLEXPART version 6.2, *Atmos. Chem. Phys.*, 5, 2461–2474, <https://doi.org/10.5194/acp-5-2461-2005>, 2005.
- Thénault, S.: Pylint, <https://www.pylint.org/>, 2001.

- van Rossum, G., Warsaw, B., and Coghlan, N.: PEP 8 – Style Guide for Python Code, Online, <https://www.python.org/dev/peps/pep-0008/>,  
1210 2001.
- Walt, S. v. d., Colbert, S. C., and Varoquaux, G.: The NumPy array: A structure for efficient numerical computation, *Computing in Science and Engineering*, 13, 22–30, <https://doi.org/10.1109/MCSE.2011.37>, 2011.
- Wolff, E.: *Continuous Delivery. Der pragmatische Einstieg*, Dpunkt Verlag, Heidelberg, 282 pp., 2014.
- Wotawa, G., Stohl, A., and Neininger, B.: The urban plume of Vienna: comparisons between aircraft measurements and photochemical  
1215 model results, *Atmospheric Environment*, 32, 2479 – 2489, [https://doi.org/https://doi.org/10.1016/S1352-2310\(98\)00021-1](https://doi.org/https://doi.org/10.1016/S1352-2310(98)00021-1), <http://www.sciencedirect.com/science/article/pii/S1352231098000211>, 1998.



**Table 1.** Overview of ECWMF data sets with associated parameters required in MARS requests (Berrisford et al., 2011; Laloyaux et al., 2016; ECMWF, 2019e, h). DET-FC stands for “Deterministic forecast”, ENS-DA for “Ensemble data assimilation”, ENS-CF for “Ensemble control forecast”, ENS-CV for “Ensemble validation forecast” and ENS-PF for “Ensemble perturbed forecast”. All times are in UTC, all steps in hours. Dates are written as DD/MM/YYYY (day optional). Steps and members are written in the format of Start/End/Step. The specifications for the operational data sets are valid for current data at the time of publication (except ENS-CV – deprecated since 8 August 2016). For details about resolution and other parameters which have changed in the course of time, see Table 2 and Table 3. The grid type for the operational data (T<sub>Coxxx</sub>) refers to the spectral cubic octahedral grid and for the reanalysis data (T<sub>Lxxx</sub>) refers to linear spherical harmonics. The identification parameter “Dataset” is to be used by public users only. Note that there is also the ERA40 reanalysis; however, as it has been superseded by ERA-Interim and ERA5 and thus rarely used nowadays, it is not included here (but flex\_extract should still be applicable).

	Operational data					Reanalyses		
	DET-FC	ENS-DA	ENS-CF	ENS-CV	ENS-PF	ERA-Interim	ERA5	CERA-20C
<b>Period of data set availability</b>								
	12/1985	22/06/2010	01/05/1994 <sup>2</sup>	12/09/2006	12/09/2006 <sup>3</sup>	01/1979	01/1979	09/1901
	– ongoing	– ongoing	– ongoing	– 08/03/2016	– ongoing	– 12/2018	– ongoing <sup>4</sup>	– 12/2010
<b>Identification</b> (MARS keywords)								
Class	od	od	od	od	od	ei	ea	ep
Stream	oper	enda/elda <sup>1</sup>	enfo	enfo	enfo	oper	oper	enda
Field type	fc/an	fc/an	cf	cv	pf	fc/an	fc/an	fc/an
Dataset	–	–	–	–	–	interim	–	cera20c
<b>Time</b> (where forecast starts or analysis is valid)								
Forecast	00/12	06/18	00/12	00/12	00/12	00/12	06/18	18
Analysis	0/6/12/18	0/6/12/18	–	–	–	0/6/12/18	0/1/.../23	0/1/.../23
<b>Step</b> (available forecast steps)								
Forecast	0/125/1	1/12/1	0/90/1	0/144/3	336	3/240/3 <sup>5</sup>	0/18/1	3/24/3
		3,6,12 <sup>7</sup>	93/144/3	150/360/6				
			150/360/6					
<b>Horizontal grid type and resolution, number of vertical levels</b>								
Grid <sup>8</sup>	T <sub>Co</sub> 1279 (0.07°)	T <sub>Co</sub> 639 (0.141°)	T <sub>Co</sub> 639 (0.141°)	T <sub>Co</sub> 639 (0.141°)	T <sub>Co</sub> 639 (0.141°)	T <sub>L</sub> 255 (0.75°)	T <sub>L</sub> 639 (0.25°)	T <sub>L</sub> 159 (1.25°)
Levels	137	137	91	91	91	60	137	91
<b>Ensemble members</b>	–	0/50/1	–	–	1/50/1	–	–	1/10/1
<b>Availability of <math>\dot{\eta}</math></b>	yes <sup>6</sup>	yes	no	no	no	no	yes	yes

<sup>1</sup> From 22/06/2010 to 18/11/2013, ENS-DA was stored in stream ENDA, afterwards in stream ELDA.  
<sup>2</sup> Exists since 11/1992, but the available dates were unregular in the beginning before 01/05/1994.  
<sup>3</sup> The data set exists from 11/1992, but model level data are available only from 12/09/2006 on.  
<sup>4</sup> Available with a delay of ca. 3 months. Fast track data with shorter delay are now also available, but subject to possible revisions  
<sup>5</sup> For public users, the forecast model level fields are not available.  
<sup>6</sup> Available as MARS parameter since 04/06/2008.  
<sup>7</sup> On 11/06/2019, the steps changed from 1/12/1 to the single steps 3,6,12.  
<sup>8</sup> See Table 4 for correspondence of grid types.

**Table 2.** List of the evolution of the spatial resolution of the IFS operational forecasts. Changes are marked in bold. The ensemble data are usually provided with higher resolution for Lag A (1–10 d) than for Lag B (10–15 d). The first part of each entry is the horizontal resolution marked with a “T” for spectral representation; with “T” representing the linear and “T<sub>Co</sub>” the cubic octahedral representation. The second part, marked with “L”, is the number of vertical model levels. In the case of ensembles, the number N of members is written in front of the resolution as N\*. Source: Palmer et al. (1997); Buizza et al. (2003); ECMWF (2019c, e, f, g).

	DET-FC	ENS-DA	ENS-CF	ENS-CV	ENS-PF
20/04/1983	<b>T106L16</b>				
13/05/1986	T106 <b>L19</b>				
17/09/1991	<b>T213L19</b>				
17/19/1991	T213 <b>L31</b>				
01/05/1994	T213L31		<b>T63L19</b>		
10/12/1996	T213L31		<b>T159L31</b>		
01/04/1998	<b>T319L31</b>		T159L31		
09/03/1999	T319 <b>L50</b>		T159L31		
12/10/1999	T319 <b>L60</b>		T159 <b>L40</b>		
21/11/2000	<b>T511L60</b>		<b>T255L40</b>		
01/02/2006	<b>T799L91</b>		<b>Lag A T399L62</b> <b>Lag B T255L62</b>		
12/09/2006	T799L91			<b>Lag A 2*T399L62</b> <b>Lag B 2*T255L62</b>	<b>Lag A 50*T399L62</b> <b>Lag B 50*T255L62</b>
26/01/2010	<b>T1279L91</b>		<b>Lag A T639L62</b> <b>Lag B T319L62</b>	Lag A 2*T <b>T639L62</b> Lag B 2*T <b>T319L62</b>	Lag A 50*T <b>T639L62</b> Lag B 50*T <b>T319L62</b>
22/06/2010	T1279L91	<b>25*T399L91</b>	Lag A T639L62 Lag B T319L62	Lag A 2*T639L62 Lag B 2*T319L62	Lag A 50*T639L62 Lag B 50*T319L62
01/11/2011	T1279L91	25*T399L91	Lag A T639L62 Lag B T319L62	Lag A 2*T639L62 Lag B 2*T319L62	Lag A 50*T639L62 Lag B 50*T319L62
25/06/2013	T1279 <b>L137</b>	25*T399 <b>L137</b>	Lag A T639L62 Lag B T319L62	Lag A 2*T639L62 Lag B 2*T319L62	Lag A 50*T639L62 Lag B 50*T319L62
19/11/2013	T1279L137	25*T399L137	Lag A T639L62 Lag B T319L62	Lag A 2*T639 <b>L91</b> Lag B 2*T319 <b>L91</b>	Lag A 50*T639L62 Lag B 50*T319L62
20/11/2013	T1279L137	25*T399L137	Lag A T639L91 Lag B T319L62	Lag A 2*T639L91 Lag B 2*T319L91	Lag A 50*T639 <b>L91</b> Lag B 50*T319 <b>L91</b>
08/03/2016	<b>T<sub>Co</sub>1279L137</b>	25*T <sub>Co</sub> <b>639L137</b>	<b>T<sub>Co</sub>639L91</b>	deprecated	50*T <sub>Co</sub> <b>639L91</b>
11/06/2019	T <sub>Co</sub> 1279L137	<b>50*T<sub>Co</sub>639L137</b>	T <sub>Co</sub> 639L91	deprecated	50*T <sub>Co</sub> 639L91

**Table 3.** List of the evolution of forecast steps and forecast start times for data sets DET-FC and ENS-CF. “Lag s” denotes different temporal resolution for forecast ranges s; “#steps” is the total number of steps. Source: (ECMWF, 2019e)

	DET-FC					ENS-CF			
	#steps	Lag 1	Lag 2	Lag 3		#steps	Lag 1	Lag 2	Lag 3
01/04/1985	20 <sup>1</sup>	12/240/12 forecast start time 12 UTC			01/04/1994	33	0/12/3	18/120/6	132/240/12
01/07/1985	30	6/144/6	156/240/12		31/07/1997	55	0/12/3	18/120/6	132/504/12
15/11/1990	32	3/12/3	18/144/6	150/240/12	09/06/1999	65	0/12/3	18/240/6	252/504/12
20/01/1999	42	3/12/3	18/240/6		25/03/2003	two forecast start times per day: 0/12 UTC			
12/09/2000	two forecast start times per day: 0/12 UTC				29/09/2004	63	0/240/6	252/504/6	
24/10/2000	52	3/72/3	78/240/6		13/09/2006	85	0/132/3	138/240/6	252/504/12
29/06/2005	85	0/132/3	138/240/6	252/504/12	22/06/2015	four forecast times per day: 0/6/12/18 UTC			
05/10/2005	87	0/144/3	150/240/6	252/504/12	"	49 (6/18 UTC)	0/144/3		
14/03/2006	57	0/96/3	102/240/6		23/11/2016	145 (0/12UTC)	0/90/1	93/144/3	150/260/6
13/09/2006	65	0/144/3	150/240/6		"	109 (6/18UTC)	0/90/1	93/144/3	
16/11/2011	125	0/90/1	93/144/3	150/240/6	–			–	

<sup>1</sup> Only surface fields.

**Table 4.** Approximate correspondences between spectral, Gaussian, and latitude / longitude grid resolutions. Source: ECMWF (2017, 2019d, e); Berrisford et al. (2011); Laloyaux et al. (2016). For the spectral grid the truncation number is denoted by “T” where the subscript “q” means quadratic grid and “l” means linear grid. The quadratic grid can not be selected with flex\_extract. The corresponding reduced Gaussian grids are denoted by “N” followed by the number of lines between the pole and the equator. The new octahedral grid is denoted by “T<sub>CO</sub>”, meaning “spectral cubic octahedral”; they correspond to a octahedral reduced Gaussian grid, denotes with an “O”.

Spectral	Gaussian Grid		Lat / Lon
T <sub>q</sub> 63	N48	209 km	1.875°
T <sub>L</sub> 95	N48	209 km	1.875°
T <sub>q</sub> 106	N80	125 km	1.125°
T <sub>L</sub> 159	N80	125 km	1.125°
T <sub>q</sub> 213	N160	63 km	0.5625°
T <sub>L</sub> 255	N128	78 km	0.75°(*)
T <sub>L</sub> 319	N160	63 km	0.5625°
T <sub>L</sub> 399	N200	50 km	0.45°
T <sub>L</sub> 511	N256	39 km	0.352°
T <sub>L</sub> 639	N320	31 km	0.25°(*)
T <sub>L</sub> 799	N400	25 km	0.225°
T <sub>L</sub> 1023	N512	20 km	0.1758°
T <sub>CO</sub> 639	O640	18 km	0.141°
T <sub>L</sub> 1279	N640	16 km	0.1406°
T <sub>CO</sub> 1279	O1280	9 km	0.07°

(\*) As GRIB1 only supports three decimals, ECMWF recommends to round the resolutions to 0.75° in the case of ERA-Interim (exact value: 0.703125°) and to 0.25° for ERA5 (exact value: 0.28125) (ECMWF, 2016a, b). See also Table 1.

**Table 5.** Directory structure of the flex\_extract v7.1 root directory.

File / subdirectory	Content	Description
Documentation/	html/	offline version of documentation
For_developers/	Flowcharts FORD Sphinx *.xls, *.sh, *	source and PNG files of flow diagrams source files for Fortran code documentation source files for documentation documentation files, scripts and info for developers
Run/	Control/ Jobscripts/ Workspace/ ECMWF_ENV run.sh run_local.sh	contains all example CONTROL files empty after distribution download; later contains korn shell job scripts not present before first local retrieval; contains downloaded data in <i>local mode</i> contains info about user credentials top-level script to start flex_extract top-level script to start flex_extract in <i>local mode</i>
Source/	Fortran Python Pythontest	complete Fortran program incl. makefiles Python source files Python unit tests
Templates/	installscript.template calc_etadot_nml.template ECMWF_ENV.template ecmwf_grib1_table_128 jobscript.template submitscript.template	template for the installation on ECMWF server namelist template for the calc_etadot program template for the ECMWF user credentials table for the assignment of parameter names and ids job script template for ECMWF batch mode before the installation took place job script template after installation (now includes settings such as version number)
Testing/	Installation Regression	data for an installation check regression test cases
CODE_OF_CONDUCT.md LICENSE.md README.md setup.sh		rules for contribution to flex_extract full licence text short introduction to flex_extract installation script

**Table 6.** Necessary account registrations per user and application mode for each data set. The registration procedure is indicated by numbers 1–3 and explained below.

Data sets	Member-state user			Public user
	Remote	Gateway	Local	Local
Operational	1	1	1, 2	-
ERA-Interim	1	1	1, 2	2
CERA-20C	1	1	1, 2	2
ERA5	1	1	3	3


  

No.	Registration procedure
1	Access as a member-state user. Account granted by the Computing Representative. Credentials have to be provided during installation.
2	Access through the ECMWF Web API. One needs to sign in at the ECMWF Web API and to configure the ECMWF key as described (ECMWF, 2019k). Member-state users can sign in with their credentials. Public users have to register for obtaining an account.
3	Access through the CDS API (Copernicus, 2019). Registration at CDS and configuration of the CDS key needed.


**Table 7.** Software dependencies for flex\_extract in all application modes.

Python	Fortran
Python3	gfortran <sup>1</sup> / CrayPE ftn <sup>2</sup>
numpy	fftw3
genshi	emoslib
ecCodes for Python (>= v2.13.0)	ecCodes for Fortran

<sup>1</sup>Remote mode / gateway mode on ecgate, and local mode. <sup>2</sup>Remote mode gateway mode on cca / ccb.



**Figure 3.** Flow diagram for the local application mode. If  $queue \neq \text{None}$ , `flex_extract` was started in remote or gateway mode and Fig. 2 applies. This is marked by the `submit` block. In the case of  $request == 1$ , `flex_extract` skips the retrieval and post-processing steps and just writes the `mars_request.csv` file. Within the local mode, the retrieval (`get_mars_data`) and post-processing (`prepare_flexpart`) parts are executed. Symbols as in Fig. 2.



**Figure 4.** General overview of the work flows and work locations in the different application modes: (a) remote, (b) gateway, and (c) local mode. The files and scripts used in each mode are outlined.



**Table 8.** Part 1 of the overview of CONTROL file parameters. A more detailed description on parameter handling, setting and value ranges is given in the supplemental material.

Parameter	Default value	Format	Description
<b>Time section</b>			
START_DATE	None	String [YYYYMMDD]	first day of retrieval period
END_DATE	None	String [YYYYMMDD]	last day of retrieval period
DATE_CHUNK	3	Integer	number of days within one MARS request
DTIME	None	Integer	time step
BASETIME	None	Integer	end time for half-day retrievals
<b>Data section</b>			
CLASS	None	String [xx]	data set class identifier in MARS archive
DATASET	None	String	public data set identifier
STREAM	None	String [xxxx]	identifier for forecasting stream
NUMBER	'OFF'	String [i/to/i]	ensemble member numbers
EXPVER	1	Integer	experiment number
FORMAT	'GRIB1'	String	output format of GRIB fields
<b>Data fields section</b>			
TYPE	None	list of strings [xx xx ... xx]	list of field type per TIME
TIME	None	list of strings [xx xx ... xx]	list of times
STEP	None	list of strings [xx xx ... xx]	list of forecast steps corresponding to TIME
MAXSTEP	None	Integer	maximum forecast step
<b>Flux data fields section</b>			
ACCTYPE	None	String	type of the flux forecast fields
ACCTIME	None	String [i/i]	forecast times of flux fields
ACCMAXSTEP	None	Integer	maximum forecast step of flux fields
RRINT	0	Integer	switch to select method for precipitation disaggregation
<b>Domain section</b>			
GRID	None	String [i/i]	horizontal resolution on longitude/latitude grid
RESOL	None	String	horizontal resolution of spectral grid
SMOOTH	0	Integer	spectral truncation of $\hat{\eta}$ on Gaussian grid
LEFT	None	String	longitude of lower left domain corner
LOWER	None	String	latitude of lower left domain corner
UPPER	None	String	latitude of upper right domain corner
RIGHT	None	String	longitude of upper right domain corner
LEVEL	None	Integer	maximum number of vertical levels
LEVELIST	None	String [start/to/end]	definition of vertical levels
<b>Vertical velocity section</b>			
GAUSS	0	Integer	switch to calculate $\dot{\eta}$
ACCURACY	24	Integer	number of bits per value in GRIB coded fields
OMEGA	0	Integer	switch to retrieve $\omega$ from MARS
OMEGADIFF	0	Integer	switch to calculate $\omega$ and $\partial p_s / \partial t$ from continuity equation
ETA	0	Integer	switch to read $\dot{\eta}$ from MARS
ETADIFF	0	Integer	switch to calculate $\dot{\eta}$ and $Dp_s / Dt$ from continuity equation
DPDETA	1	Integer	switch to select multiplication of $\dot{\eta}$ by $\partial p / \partial \eta$
ETAPAR	77	Integer	GRIB parameter id for $\dot{\eta} / \partial p / \partial \eta$

**Table 8.** Part 2 of the overview of CONTROL file parameters.

Parameter	Default value	Format	Description
<b>General section</b>			
DEBUG	0	Integer	switch to save the temporary files
REQUEST	0	Integer	switch to create the file <code>mars_requests.csv</code>
PUBLIC	0	Integer	switch to select public Web API access
OPER	0	Integer	switch to prepare operation job script
ECSTORAGE	0	Integer	switch to store results in ECFS file system
ECTRANS	0	Integer	switch to transfer final files to local system
PREFIX	'EN'	String	front string in file names before the date string
ECFSDIR	'ectmp:/\$USER/ econdemand/'	String	destination directory on ECFS file system
MAILFAIL	[ '\$USER' ]	List of strings	list of emails to send log files to
MAILOPS	[ '\$USER' ]	List of strings	list of emails to send log files to
<b>Additional data section</b>			
CWC	0	Integer	switch to retrieve total cloud water content
DOUBLEELDA	0	Integer	switch to manually double ensemble member number
ADDPAR	None	String [p1/p2/.../pn]	additional surface fields to retrieve

**Table 9.** Description of the parameters stored in file `ECMWF_ENV`.

Parameter	Default value	Format	Description
ECUID	None	String	ECMWF user id
ECGID	None	String	ECMWF group id
DESTINATION	None	String	ectrans association
GATEWAY	None	String	name or ip address of member gateway server

**Table 10.** Overview of templates used in `flex_extract`. They are stored in the `Templates` directory.

Template	Description
<code>calc_etadot_nml.template</code>	Used to create a Fortran namelist file called <code>fort.4</code> . It will be created in the Python part and contains controlling options for <code>calc_etadot</code> . (See Table 14)
<code>ecmwf_env.template</code>	Used to create the <code>ECMWF_ENV</code> file within application modes gateway and remote.
<code>installscript.template</code>	Used to create the file <code>compilejob.ksh</code> during the installation process for the application modes remote and gateway.
<code>jobscript.template</code>	Used to create the template <code>submitjob.template</code> in the installation process. A couple of parameters are set, such as the user credentials and the <code>flex_extract</code> version number.
<code>submitjob.template</code>	Used to create the actual job script file called <code>job.ksh</code> for the execution of <code>flex_extract</code> in the application modes remote and gateway.

**Table 11.** Overview of parameters to be set in the `setup.sh` script for installation. In remote and local mode for member-state users, the file `ECMWF_ENV` will be created, hence the parameters from Table 9 must also be set in the `setup.sh` script.


Parameter	Default value	Format	Description
<code>TARGET</code>	None	String	defines location and therefore the application mode
<code>MAKEFILE</code>	None	String	Makefile for compiling <code>calc_etadot</code>
<code>JOB_TEMPLATE</code>	<code>jobscript.template</code>	String	batch job template for gateway and remote mode
<code>INSTALLDIR</code>	<code>\$HOME</code> on ECMWF servers; <code>pwd</code> in local mode	String	root path for <code>flex_extract</code> working directory
<code>CONTROLFILE</code>	<code>CONTROL_ERA5</code>	String	input file with parameter settings

**Table 12.** Overview of the parameter to be set in the `run*.sh` script. In order to provide a complete list, some already defined parameters from Tables 8 and 11 are repeated here. In the case of a special format, a sample format is given in parentheses; f denotes a floating-point number.


Parameter	Default value	Format	Description
START_DATE	None	String (YYYYMMDD)	first day of retrieval period
END_DATE	None	String (YYYYMMDD)	last day of retrieval period
DATE_CHUNK	3	Integer	number of days within one MARS request
BASETIME	None	Integer	end time for half-day retrievals
STEP	None	blank separated list of numbers	list of forecast steps of corresponding retrieval times
LEVELIST	None	String (start/to/end)	defines list of vertical levels
JOB_CHUNK	None	Integer	number of days to be retrieved within a single job
AREA	-	String (f/f/f/f)	domain defined as north/west/south/east
PUBLIC	0	Integer	set to 1 for using public access mode
INPUTDIR	None	String	path to temporary working directory
OUTPUTDIR	None	String	path where final output files are stored
PPID	None	Integer	parent process id of the job (only for debugging)
JOB_TEMPLATE	<code>submitjob.template</code>	String	job template file for ECMWF batch queue
QUEUE	None	String	in case of non-local mode, the ECMWF server name
CONTROLFILE	<code>CONTROL_ERA5</code>	String	input file with parameter settings
RRINT	0	Integer	set to 1 to select new method for precipitation disaggregation
REQUEST	0	Integer	set to 1 to create the file <code>mars_requests.csv</code>
OPER	0	Integer	set to 1 for operational mode (job script)
DEBUG	0	Integer	set to 1 to save the temporary files

**Table 13.** List of flux fields retrieved by `flex_extract` and the disaggregation schemes (precip: Eq. 1 or Sect. 3.6.2, flux: Eq. 4) applied.

Short name	Name	Unit	Disaggregation
LSP	large-scale precipitation	m	precip
CP	convective precipitation	m	precip
SSHF	surface sensible heat flux	Jm <sup>-2</sup>	flux
EWSS	eastward turbulent surface stress	Nm <sup>-2</sup> s	flux
NSSS	northward turbulent surface stress	Nm <sup>-2</sup> s	flux
SSR	surface net solar radiation	Jm <sup>-2</sup>	flux



**Figure 5.** Example of disaggregation scheme as implemented in older versions of flex\_extract for an isolated precipitation event lasting one time interval (thick blue line). The amount of original precipitation after de-accumulation is given by the blue-shaded area. The green circles represent the discrete grid points after disaggregation. FLEXPART interpolates linearly between them as indicated by the green line and the green-shaded area. Note that supporting points for the interpolation are shifted by half a time interval compared to the other meteorological fields. From Hittmeir et al. (2018).



**Figure 6.** As Figure 5, but with the new interpolation scheme using additional sub-grid points. From Hittmeir et al. (2018).

**Table 14.** Overview of options controlling `calc_etadot`. Note that the resolution of the latitude-longitude grid is given implicitly by the grid dimensions and extent.

Parameter	Description	Remarks
<code>maxl</code>	grid dimension – longitudes	
<code>maxb</code>	grid dimension – latitudes	
<code>mlevel</code>	grid dimension – number of levels	
<code>mlevelist</code>	list of levels	to be given in MARS request notation like <code>1/10/91</code>
<code>mnauf</code>	number of spectral coefficients in input data	
<code>metapar</code>	GRIB ID of vertical velocity in output	standard FLEXPART expects =77
<code>rlo0</code>	Western border of domain in degree	
<code>rlo1</code>	Eastern border of domain in degree	
<code>rla0</code>	Southern border of domain in degree	
<code>rla1</code>	Northern border of domain in degree	
<code>momega</code>	if 1, $\omega$ is calculated from $\dot{\eta}$ and output	for testing the accuracy of calculated $\dot{\eta}$ if no $\dot{\eta}$ from MARS is available
<code>momegadiff</code>	if 1, calculated $\omega$ is compared with $\omega$ from MARS	
<code>mgauss</code>	if 1, evaluate continuity equation on GG	
<code>msmooth</code>	if $\neq 0$ , apply spectral smoothing by clipping at given truncation	
<code>meta</code>	if 1, use $\dot{\eta}$ from input.	
<code>metadiff</code>	if 1 and <code>meta</code> =0, $\dot{\eta}$ needs to be available from MARS and this is compared with calculated $\dot{\eta}$	for testing the accuracy of $\dot{\eta}$ calculation
<code>mdpdeta</code>	if 1, give $\dot{\eta}_p$ as output	with the current version of FLEXPART, only =1 is useful; future versions might use $\dot{\eta}$ .

**Table 15.** Determination of the method for obtaining  $\dot{\eta}$  in `calc_etadot` as a funtion of control parameters (see also Table 14). GG stands for Gaussian grid. The names of the corresponding regression tests (see Sect. 5.4) are also given

Method	mgauss	meta	Test name
Continuity eq. on lat-lon grid	0	0	latlon
Continuity eq. on GG	1	0	gauss
Use $\dot{\eta}$ from input	0	1	etadot
(Program will stop with ERROR)	1	1	–

**Table 16.** List of `fort` files generated by the Python part to serve as input for the Fortran program, and the output file of `calc_etadot`. If the optional fields were not extracted, the corresponding files are empty.

Number	Content
<b>Input to the Fortran program <code>calc_etadot</code></b>	
10	U and V wind components
11	temperature
12	logarithm of surface pressure
13	divergence (optional)
16	surface fields
17	specific humidity
18	surface specific humidity (reduced Gaussian)
19	vertical velocity (pressure) (optional)
21	eta-coordinate vertical velocity (optional)
22	total cloud water content (optional)
<b>Output from Fortran program <code>calc_etadot</code></b>	
15	U and V wind components, $\dot{\eta}$ , temperature, surface pressure, specific humidity

**Table 17.** List of model level parameters FLEXPART requires to run and the availability in the different data sets (ECMWF, 2019e, i). The cloud-water content fields are optional. The divergence and logarithm or surface pressure fields are only necessary for the calculation of the vertical velocity when  $\dot{\eta}$  is not available directly. These fields are not transferred to the FLEXPART input files. FC stands for “forecast” and AN for “analysis”.

Variables	Short name	Parameter ID	Unit	Operational		ERA-Interim		ERA5		CERA-20C	
				FC	AN	FC	AN	FC	AN	FC	AN
Temperature	T	130	K	x	x	x	x	x	x	x	x
Specific humidity	Q	133	kgkg <sup>-1</sup>	x	x	x	x	x	x	x	x
U – wind component	U	131	ms <sup>-1</sup>	x	x	x	x	x	x	x	x
V – wind component	V	132	ms <sup>-1</sup>	x	x	x	x	x	x	x	x
Eta-coordinate vertical velocity	etadot	77	s <sup>-1</sup>	x <sup>2</sup>	x <sup>2</sup>	-	-	x	x	x	x
Divergence	D	155	kgm <sup>-2</sup>	x	x	x	x	x	x	x	x
Specific cloud liquid water content	clwc	246	kgkg <sup>-1</sup>	x	x	x	x	x	x	x	x
Specific cloud ice water content	ciwc	247	kgkg <sup>-1</sup>	x	x	x	x	x	x	x	x
Logarithm of surface pressure <sup>1</sup>	lnsp	152	-	(x)	(x)	(x)	(x)	(x)	(x)	(x)	(x)

<sup>1</sup>Only available on model level 1.

<sup>2</sup>Available from 4 June 2008 onward.



**Table 18.** List of surface level parameters FLEXPART requires to run and their availability from different data sets (ECMWF, 2019e, i). FC stands for “forecast” and AN for “analysis”. Special or future versions of FLEXPART or pre/post-processing software may require additional surface level fields which are not listed here.

Variables	Short name	Parameter ID	Unit	Operational		ERA-Interim		ERA5		CERA-20C	
				FC	AN	FC	AN	FC	AN	FC	AN
2 metre temperature	2t	167	K	x	x	x	x	x	x	x	x
2 metre dewpoint temperature	2d	168	K	x	x	x	x	x	x	x	x
10 metre U wind component	10u	165	ms <sup>-1</sup>	x	x	x	x	x	x	x	x
10 metre V wind component	10v	166	ms <sup>-1</sup>	x	x	x	x	x	x	x	x
Geopotential	z	129	m <sup>-2</sup> s <sup>-2</sup>	x	x	x	x	x	x	x	x
Land-Sea Mask	lsm	172	0 – 1	x	x	x	x	x	x	x	x
Mean sea level pressure	msl	151	Pa	x	x	x	x	x	x	x	x
Snow depth	sd	141	m of w. eq.	x	x	x	x	x	x	x	x
Standard deviation of orography	sdor	160	-	-	x	-	x	-	x	-	x
Surface pressure	sp	134	Pa	-	x	x	x	-	x	x	x
Total cloud cover	tcc	164	0 – 1	x	x	x	x	x	x	x	x
Convective precipitation	cp	143	m	x	-	x	-	x	-	x	-
Large-scale precipitation	lsp	142	m	x	-	x	-	x	-	x	-
Surface sensible heat flux	sshf	146	Jm <sup>-2</sup>	x	-	x	-	x	-	x	-
Eastward turbulent surface stress	ewss	180	Nm <sup>-2</sup> s	x	-	x	-	x	-	x	-
Northward turbulent surface stress	nsss	181	Nm <sup>-2</sup> s	x	-	x	-	x	-	x	-
Surface net solar radiation	ssr	176	Jm <sup>-2</sup>	x	-	x	-	x	-	x	-
Forecast surface roughness <sup>1</sup>	fsr	244	m	x	-	-	-	x	x	x	x

<sup>1</sup>Necessary in CERA-20C due to missing surface roughness parameter

**Table 19.** Basic metrics.

Version	LOC	SLOC	Comments	Multi	Blank
7.0.4	2538	1820	346	13	374
7.1	7543	2842	1072	2265	1397

**Table 20.** Ranks of cyclomatic complexity (CC) taken from the manual of the Python package `radon` (Lacchia, 2019).

CC score	Rank	Risk
1 - 5	A	low – simple block
6 - 10	B	low – well structured and stable block
11 - 20	C	moderate – slightly complex block
21 - 30	D	more than moderate – more complex block
31 - 40	E	high – complex block, alarming
41+	F	very high – error-prone, unstable block